

Quantum Dissipative Systems and Feedback Control Design by Interconnection

Matthew R. James, John Gough

Abstract

The purpose of this paper is to give a description of quantum dissipative systems that combines perspectives from the quantum physics and control engineering communities. The resulting theory provides useful methods for analysis and design of dissipative quantum systems. We describe the interaction of the plant and a class of exosystems in general quantum network terms. Our results include an infinitesimal characterization of the dissipation property, which generalizes the well-known Positive Real and Bounded Real Lemmas, and is used to study some properties of quantum dissipative systems. We also show how to formulate control design problems using quantum network models, which implements Willems' "control by interconnection" for open quantum systems. This control design formulation includes, for example, standard problems of stabilization, regulation, robust control.

Keywords: Quantum feedback control, dissipation, damping, networks, control by interconnection, regulation, stabilization, robustness.

I. INTRODUCTION

Phenomena of *dissipation* or *damping* are fundamental in physics and engineering, and have been the subject of extensive investigations. In physics, methods have been developed to model energy loss and decoherence arising from the interaction of a system with an environment, or heat bath, [15], [9], [1], [10]. In particular, models which preserve canonical structure are very important. In quantum mechanics, this implies preservation of commutation relations, and so an essential feature of quantum mechanics is respected. Canonical models efficiently capture the physics of energy flows, and this feature makes them very useful for modelling and gaining physical insight. An important consequence of this energy bookkeeping is that systems which dissipate energy are inherently stable. This fact has been generalized and forms the basis of Lyapunov methods for stability analysis of dynamical systems. From a control design perspective there is another important reason why preservation of canonical structure is important, namely this property ensures that controller designs can (in principle) be physically realized—this is vital when we wish, for instance, the controller to be itself a quantum system, [17], [32], [16].

In control engineering, physical ideas were abstracted by Willems [27] to develop a theory of dissipative systems which applies to a wide range of systems that are not necessarily systems described by classical Lagrangian or Hamiltonian mechanics. This theory applies to open systems [29], whereas Lyapunov methods apply to closed systems. The theory of dissipative systems and the methods developed from it are widely used in control system analysis and design. Included in this list are methods for stability analysis, e.g. [18], [13], [14], and control design by energy shaping, interconnection, and robust control system design; e.g. [20], [26], [28], [29], [22], [30].

The purpose of this paper is to merge together these two lines of thinking concerning dissipative systems, and thereby provide useful methods for analysis and design of dissipative quantum systems. To this end, we represent the system (the *plant*) and its environment (the *exosystem*) as a *network*, employing the framework of [11], which extends [8], [2]. Such networks are themselves open quantum systems, and components may interact via field-mediated interactions, which have a natural input-output structure, and also directly via an interaction Hamiltonian, which does not necessarily have an input-output structure. We allow the exosystem to vary in a class of such exosystems, and the dissipation inequality we define is expressed in these terms. This network description turns out to be very appropriate and efficient, and was inspired by the behavioral "control as interconnection" perspective in Willems' more recent work, [28], [29] (also [24], [25], [31]). We provide an infinitesimal characterization of the dissipation property, and this important tool is used indispensably in this paper. This characterization includes generalizations of the well-known Positive Real and Bounded Real Lemmas, and is used to study some properties of quantum dissipative systems. We show that essentially all open quantum systems are dissipative for a suitable choice of supply rate. This "natural" supply rate includes terms corresponding to the classical notion of *passivity*, a dissipation or damping term due to the quantum noise, and a dissipative term which is present in general when the exosystem does not commute with the plant. The merger of the quantum physics and the control engineering perspectives is evident in this supply rate. The passivity term will be familiar to control engineers, the quantum dissipation term will be familiar to physicists, and perhaps the third exosystem dissipation term will be new to both communities.

Our modeling of dissipative quantum systems has its origins in the papers [6], [5], [3], [16], and represents inputs as the sum of a quantum noise term, used in physics to describe damping as mentioned above, and a signal term of the type used by Willems to provide a means for the external world to influence the system. This signal plus noise representation arises

M.R. James is with the Department of Engineering, Australian National University, Canberra, ACT 0200, Australia. Matthew.James@anu.edu.au. Research supported by the Australian Research Council.

J. Gough is with the Institute for Mathematical and Physical Sciences, University of Wales, Aberystwyth, Ceredigion, SY23 3BZ, Wales. jug@aber.ac.uk

in a natural way from the unitary models we use. Unitary models for open quantum systems were developed in the physics literature to describe systems interacting with an environment, or field, often ideally represented as an infinite heat bath; see, e.g. [19], [33], [9], [1], [10]. This interaction was expressed in input output terms, due to the underlying causal structure. Such unitary descriptions preserve the canonical structure of quantum mechanics, and in particular, preserve the commutation relations. Open quantum models are unitary models that provide a description of the system of interest (e.g. optical cavity, atom, etc) as well as the environment (e.g. optical field). The signal component of the input comes from the output of another system, namely an exosystem.

The framework we have developed, which describes how systems can be influenced by their environment, can also be used to describe how systems are influenced by controllers, and hence is useful for control design by interconnection, [28], [29], and various passivity-based methods [20], [26], [21], [22]. We give a general description of how to formulate control design problems in these terms. This description includes, for example, standard problems of stabilization, regulation, and robust control.

Note that issues of stability are important in the analysis and design of quantum networks. This is because quantum networks may contain active elements that introduce energy, and whenever this happens, stability of feedback loops in the network is a basic consideration (small gain theorem, [34], [35], [3]). Energy may be introduced by design, such as via an amplifier, or by accident due to undesirable environmental influences. It also plays a role in regulation of a system to a desired equilibrium mode of operation.

We begin in section II by describing the mathematical models we use, which are expressed in terms of the quantum stochastic calculus, [15], [9]. In particular, concatenations and series connections of systems are reviewed. Our main definitions and results for quantum dissipative systems are given in section III, which includes some examples for illustration. Section IV contains a formulation of control by interconnection methodology for quantum dissipative systems, which we illustrate using simple examples. The appendix contains some mathematical definitions and results needed in the paper.

II. OPEN QUANTUM SYSTEMS

A. Definition

In this paper we consider a class of open quantum systems, [15], [9], [23], [10]. We denote these systems by an $(1+n) \times (1+n)$ matrix of parameters (Ito generator matrix [11])

$$\mathbf{G} = \begin{pmatrix} -\frac{1}{2}\mathbf{L}^\dagger\mathbf{L} - iH & -\mathbf{L}^\dagger\mathbf{S} \\ \mathbf{L} & \mathbf{S} - \mathbf{I} \end{pmatrix}. \quad (1)$$

We now explain the meaning of the notation use here. The system is assumed to be defined on a Hilbert space \mathfrak{h} , on which are defined linear operators which constitute the entries of \mathbf{G} . We use the symbol \mathcal{A} to denote the algebra of (bounded) operators on \mathfrak{h} . The operator $H \in \mathcal{A}$ is self-adjoint; i.e. $H = H^*$, where H^* is the Hilbert space adjoint, \mathbf{L} is a (column) vector of operators in \mathcal{A} of length n , and \mathbf{S} is an $n \times n$ matrix of operators in \mathcal{A} satisfying $\mathbf{S}^\dagger\mathbf{S} = \mathbf{S}\mathbf{S}^\dagger = \mathbf{I}$ where, for any matrix \mathbf{M} of operators $\mathbf{M}^\dagger = (\mathbf{M}^*)^T$ (conjugate transpose). Also, $i = \sqrt{-1}$ and \mathbf{I} is the identity matrix.

Physically, \mathbf{G} represents a quantum system with Hamiltonian H coupled to a (multichannel) vacuum quantum noise field $\hat{\mathbf{A}} = \{A_{\alpha\beta}\}_{\alpha,\beta=0,1,\dots,n}$ (the index 0 refers to the first row or column) through interaction operators \mathbf{L} and scattering matrix \mathbf{S} . Before we can discuss the dynamics of the open system, we need to describe the quantum noise field $\hat{\mathbf{A}}$, which is an $(1+n) \times (1+n)$ matrix of field operators (depending on time t) defined on a suitable boson Fock space given by

$$\hat{\mathbf{A}}(t) = \begin{pmatrix} t & \mathbf{A}^T(t) \\ \mathbf{A}^*(t) & \mathbf{\Lambda}(t) \end{pmatrix}. \quad (2)$$

Here, \mathbf{A} is a (column) vector (of length n) of annihilation operators, and $\mathbf{\Lambda}$ is an $n \times n$ matrix of scattering operators. The non-zero Ito products are

$$du_{\alpha\beta}(t) du_{\mu\nu}(t) = \hat{\delta}_{\beta\mu} du_{\alpha\nu}(t) \quad (3)$$

where

$$\hat{\delta}_{\alpha\beta} = \begin{cases} 1, & \alpha = \beta \in \{1, \dots, n\}; \\ 0, & \text{otherwise.} \end{cases}$$

The dynamics of the system \mathbf{G} is given in terms of the unitary evolution of arbitrary system operators $X \in \mathcal{A}$: $X(t) = V^*(t)XV(t)$, where the unitary operator $V(t)$ is given by

$$dV(t) = \text{tr}[\mathbf{G}d\hat{\mathbf{A}}(t)]V(t). \quad (4)$$

By the quantum Ito rule, we have

$$\begin{aligned} dX(t) &= (\mathcal{L}_{\mathbf{L}(t)}(X(t)) - i[X(t), H(t)])dt \\ &\quad + d\mathbf{A}^\dagger(t)\mathbf{S}^\dagger(t)[X(t), \mathbf{L}(t)] + [\mathbf{L}^\dagger(t), X(t)]\mathbf{S}(t)d\mathbf{A}(t) + \text{tr}[(\mathbf{S}^\dagger(t)X(t)\mathbf{S}(t) - X(t))d\mathbf{\Lambda}(t)]. \end{aligned} \quad (5)$$

In this expression, all operators including the entries of \mathbf{G} evolve unitarily, e.g. $\mathbf{L}(t) = V^*(t)\mathbf{L}V(t)$. The notation $[A, B] = AB - BA$ denotes the commutator of two operators, and commutators of operators and vectors of operators are defined component-wise. We also employ the notation

$$\mathcal{L}_{\mathbf{L}}(X) = \frac{1}{2}\mathbf{L}^\dagger[X, \mathbf{L}] + \frac{1}{2}[\mathbf{L}^\dagger, X]\mathbf{L} = \sum_{j=1}^n \left(\frac{1}{2}L_j^*[X, L_j] + \frac{1}{2}[L_j^*, X]L_j \right).$$

Given a system \mathbf{G} , we write

$$\mathcal{G}_{\mathbf{G}}(X) = \mathcal{L}_{\mathbf{L}}(X) - i[X, H] \quad (6)$$

for the associated Lindblad generator, which is independent of the scattering parameter \mathbf{S} (recall that the inputs are vacuum).

The output field is defined by $\tilde{\hat{\mathbf{A}}}(t) = V^*(t)\hat{\mathbf{A}}(t)V(t)$ and satisfies the equation

$$d\tilde{\hat{\mathbf{A}}}(t) = \mathbf{M}^*(t)d\hat{\mathbf{A}}(t)\mathbf{M}^T(t) \quad (7)$$

where

$$\mathbf{M} = \begin{pmatrix} 1 & 0 \\ \mathbf{L} & \mathbf{S} \end{pmatrix}, \quad (8)$$

the Galilean matrix associated with \mathbf{G} , [11].

In this paper we abuse notation slightly and write

$$\mathbf{G} = (\mathbf{S}, \mathbf{L}, H)$$

to denote the matrix defined by (1). In fact, we often refer to the system specified by \mathbf{G} simply as \mathbf{G} .¹

Remark 2.1: Here, we have taken the input field to be in a canonical vacuum state. This is without loss of generality, since, for example, coherent and thermal states can be represented in terms of vacuum states and possible additions to the system parameters. \square

We close this subsection by describing an important property of the unitary open system dynamics (5) which will be used in the sequel. Associated with the quantum noise process $\hat{\mathbf{A}}(t)$ is a filtration $\mathcal{U}_t \subset \mathcal{A} \otimes \mathcal{F}$, $\mathcal{U}_0 = \mathcal{A}^2$, with respect to which $X(t)$ is adapted, i.e. $X(t) \in \mathcal{U}_t$. There is an associated *vacuum expectation* $\mathbb{E}_t : \mathcal{A} \otimes \mathcal{F} \rightarrow \mathcal{U}_t$ [23, Chapter 26] with respect to which the open dynamics satisfies

$$\mathbb{E}_s[X(t)] = X(s) + \int_s^t \mathbb{E}_s[\mathcal{G}_{\mathbf{G}}(X(r))] dr \quad (9)$$

for all $t \geq s$.

B. Concatenations and Interconnections of Systems

In order to describe and manipulate networks of open quantum systems, it is helpful to be able to concatenate, decompose, and interconnect systems. Systems may be interconnected using direct Hamiltonian interactions, and/or field-mediated interactions. These issues are discussed in detail in [11] (which builds on the cascade theory for open systems [8], [2]), and here we summarize the basic constructions needed for this paper.

We assume that a network consists of systems defined on a suitably large Hilbert space, which may, for example, be the tensor product of the Hilbert spaces of the components. When building a network, we can enlarge the Hilbert space as needed. The network is itself regarded as a system, with unitary dynamics as discussed in the previous subsection.

Given two systems $\mathbf{G}_1 = (\mathbf{S}_1, \mathbf{L}_1, H_1)$ and $\mathbf{G}_2 = (\mathbf{S}_2, \mathbf{L}_2, H_2)$, we define their *concatenation* to be the system $\mathbf{G}_1 \boxplus \mathbf{G}_2$ by

$$\mathbf{G}_1 \boxplus \mathbf{G}_2 = \left(\begin{pmatrix} \mathbf{S}_1 & 0 \\ 0 & \mathbf{S}_2 \end{pmatrix}, \begin{pmatrix} \mathbf{L}_1 \\ \mathbf{L}_2 \end{pmatrix}, H_1 + H_2 \right). \quad (10)$$

When a system is such that the scattering matrix has a block diagonal structure, one can decompose it as a concatenation of subsystems. If the systems have n_1 and n_2 dimensional inputs, respectively, then $\mathbf{G}_1 \boxplus \mathbf{G}_2$ will be a $(1 + n_1 + n_2)$ -square matrix. It is possible to include zero-dimensional inputs into this scheme as a special case: if a system in isolation has no inputs then it is a closed dynamical system and its dynamics are described by a Hamiltonian H . It is convenient just to write this as $\mathbf{G} = (-, -, H)$ with the absence of inputs denoted by blanks; we then just set $(-, -, H) \boxplus (-, -, H') := (-, -, H + H')$ and more generally $(-, -, H) \boxplus (S', \mathbf{L}', H') = (S', \mathbf{L}', H') \boxplus (-, -, H) := (S', \mathbf{L}', H + H')$.

¹This is somewhat analogous to the common practice of referring to the classical linear system $G : \dot{x} = Ax + Bu, y = Cx + Du$ by the matrix $G = \begin{pmatrix} A & B \\ C & D \end{pmatrix}$ or by the transfer function $G(s) = C(sI - A)^{-1}B + D$.

² \mathcal{U}_t is the von Neumann algebra generated by the initial operators and the noises up to time t .

When the systems $\mathbf{G}_1 = (\mathbf{S}_1, \mathbf{L}_1, H_1)$ and $\mathbf{G}_2 = (\mathbf{S}_2, \mathbf{L}_2, H_2)$ have the same number of field channels, we can form a series connection by connecting the output of, say, system 1 into the input of system 2. This is described by the *series product* $\mathbf{G}_2 \triangleleft \mathbf{G}_1$ defined by

$$\mathbf{G}_2 \triangleleft \mathbf{G}_1 = (\mathbf{S}_2 \mathbf{S}_1, \mathbf{L}_2 + \mathbf{S}_2 \mathbf{L}_1, H_1 + H_2 + \frac{1}{2i}(\mathbf{L}_2^\dagger \mathbf{S}_2 \mathbf{L}_1 - \mathbf{L}_1^\dagger \mathbf{S}_2^\dagger \mathbf{L}_2)). \quad (11)$$

This models *field-mediated interactions*.

Direct Hamiltonian interactions between systems $\mathbf{G}_1 = (\mathbf{S}_1, \mathbf{L}_1, H_1)$ and $\mathbf{G}_2 = (\mathbf{S}_2, \mathbf{L}_2, H_2)$ are given by an interaction Hamiltonian H_{int} , which we can express with the aid of an auxiliary system $\mathbf{G}_{int} = (-, -, H_{int})$ as

$$\mathbf{G}_1 \boxplus \mathbf{G}_2 \boxplus \mathbf{G}_{int}. \quad (12)$$

It is important to note that we have *not* assumed that operators in different subsystems commute. Indeed, we wish to explicitly include cases where subsystems do not commute.

A system $\mathbf{G} = (\mathbf{S}, \mathbf{L}, H)$ is called *reducible* system [11] if it can be expressed as a *decomposition*

$$\mathbf{G} = \boxplus_j \mathbf{G}_j, \quad (13)$$

where the decomposition is relative to a block diagonal representation $\mathbf{S} = \text{diag}(\mathbf{S}_1, \dots, \mathbf{S}_d)$, so that $\mathbf{G}_j = (\mathbf{S}_j, \mathbf{L}_j, H_j)$. Such decompositions are not unique, and the subsystems need not commute.

Field mediated interactions relative to the decomposition (13) are specified by a *list of series connections*

$$\mathcal{S} = \{\mathbf{G}_j \triangleleft \mathbf{G}_k\} \quad (14)$$

representing series pairs $\mathbf{G}_j \triangleleft \mathbf{G}_k$, such that (i) the field dimensions of the members of each pair are the same, and (ii) each input and each output (relative to the decomposition (13)) has at most one connection. Such a list of series connections is said to be *compatible with the decomposition (13)*. By applying the series product a number of times, a decomposition $\boxplus_j \mathbf{G}_j$, an interaction Hamiltonian H_{int} , and a compatible list of series connections $\{\mathbf{G}_j \triangleleft \mathbf{G}_k\}$ determines a network \mathbf{N} which is itself a reducible system, [11, Theorem 3.7]. Such networks are called *reducible*.

In particular, given two reducible systems $\mathbf{P} = \boxplus_j \mathbf{P}_j$ and $\mathbf{G} = \boxplus_{j'} \mathbf{G}_{j'}$, an interaction Hamiltonian

$$K = -i \sum_k (N_k^* M_k - M_k^* N_k),$$

where $N_k \in \mathcal{A}_{\mathbf{P}}$, $M_k \in \mathcal{A}_{\mathbf{G}}$, and a list of series connections $\mathcal{S} = \{\mathbf{G}_k \triangleleft \mathbf{P}_j, \mathbf{P}_{k'} \triangleleft \mathbf{G}_{j'}\}$, one can form a network $\mathbf{N} = \mathbf{P} \wedge \mathbf{G}$ (here we use the wedge notation from [28] for interconnections of systems). This type of network will be used extensively in what follows. An example is shown in Figure 1.




Fig. 1. The network $\mathbf{P} \wedge \mathbf{G} = \mathbf{P}_1 \boxplus (\mathbf{P}_3 \triangleleft \mathbf{G}_1 \triangleleft \mathbf{P}_2) \boxplus \mathbf{G}_2 \boxplus K$ specified by the interaction Hamiltonian K and series list $\{\mathbf{G}_1 \triangleleft \mathbf{P}_2, \mathbf{P}_3 \triangleleft \mathbf{G}_1\}$.

For future reference, we mention that the Lindblad generators for the systems formed with the concatenation and series products are

$$\mathcal{G}_{\mathbf{G}_1 \boxplus \mathbf{G}_2}(X) = \mathcal{L}_{\mathbf{L}_1}(X) + \mathcal{L}_{\mathbf{L}_2}(X) - i[X, H_1 + H_2] = \mathcal{G}_{\mathbf{G}_1}(X) + \mathcal{G}_{\mathbf{G}_2}(X), \quad (15)$$

$$\begin{aligned} \mathcal{G}_{\mathbf{G}_2 \triangleleft \mathbf{G}_1}(X) &= \mathcal{L}_{\mathbf{L}_2 + \mathbf{S}_2 \mathbf{L}_1}(X) - i[X, H_1 + H_2 + \frac{1}{2i}(\mathbf{L}_2^\dagger \mathbf{S}_2 \mathbf{L}_1 - \mathbf{L}_1^\dagger \mathbf{S}_2^\dagger \mathbf{L}_2)] \\ &= \mathcal{L}_{\mathbf{S}_2 \mathbf{L}_1}(X) + \mathcal{L}_{\mathbf{L}_2}(X) + \mathbf{L}_1^\dagger \mathbf{S}_2^\dagger [X, \mathbf{L}_2] + [\mathbf{L}_2^\dagger, X] \mathbf{S}_2 \mathbf{L}_1 - i[X, H_1 + H_2] \\ &= \mathcal{L}_{\mathbf{L}_1}(X) + \mathcal{L}_{\mathbf{L}_2}(X) + \mathbf{L}_1^\dagger (\mathbf{S}_2^\dagger X \mathbf{S}_2 - X) \mathbf{L}_1 + \mathbf{L}_1^\dagger \mathbf{S}_2^\dagger [X, \mathbf{L}_2] + [\mathbf{L}_2^\dagger, X] \mathbf{S}_2 \mathbf{L}_1 - i[X, H_1 + H_2]. \end{aligned} \quad (16)$$

III. QUANTUM DISSIPATIVE SYSTEMS

A. Definitions and Differential Characterization

A *plant* \mathbf{P} is an open system of the type defined in subsection II-A:

$$\mathbf{P} = (\mathbf{S}, \mathbf{L}, H). \quad (17)$$

It is the system of main interest, and is regarded as being part of a possibly larger network of systems. Entries in the matrix \mathbf{P} belong to an algebra $\mathcal{A}_{\mathbf{P}}$. Our interest in this section is in modeling and analyzing the effect of the network on the plant. Accordingly, we assume that the plant is reducible (recall subsection II-B), and that certain of its input and outputs are available for connection to an *exosystem* \mathbf{W} , an open system

$$\mathbf{W} = (\mathbf{R}, \mathbf{w}, D). \quad (18)$$

It is also assumed that certain plant variables are available for direct interconnection with an exosystem. Thus the plant definition and interconnection specification determine how it can interface with exosystems \mathbf{W} , as discussed in subsection II-B. The interconnections determine a network $\mathbf{P} \wedge \mathbf{W}$. We will allow exosystems \mathbf{W} to vary in a class \mathcal{W} of such exosystems. The operators constituting the matrix \mathbf{W} belong to an algebra $\mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{ex}$. The input to the system $\mathbf{P} \wedge \mathbf{W}$ is a canonical vacuum field, although this can be relaxed, as discussed above.

Let $r = r_{\mathbf{P}}(\mathbf{W}) \in \mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{ex}$ be a self-adjoint symmetrically ordered function of the exosystem parameters, depending on the plant parameters (e.g. a quadratic form), called a *supply rate*. In general, a supply rate may contain constant terms (see Example 3.13).

We say that the plant \mathbf{P} is *dissipative* with supply rate r with respect to a class \mathcal{W} of exosystems if there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ such that

$$\mathbb{E}_0 \left[V(t) - V - \int_0^t r(\mathbf{W})(s) ds \right] \leq 0 \quad (19)$$

for all exosystems $\mathbf{W} \in \mathcal{W}$ and all $t \geq 0$. Here, the dynamics is that of the network $\mathbf{P} \wedge \mathbf{W}$, \mathbb{E}_0 is the initial vacuum expectation onto $\mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{ex}$ (which contains $\mathcal{A}_{\mathbf{P}}$), and \leq denotes operator ordering, see the Appendix.

We shall refer to (19) as the *dissipation inequality*. It is a natural generalization of Willems' definition [27] to open quantum systems (see Remark 3.3), building on [5], [16]. Following the terminology from [27], when equality holds in (19) for all exosystems $\mathbf{W} \in \mathcal{W}$, we say that the plant \mathbf{P} is *lossless*. This terminology refers to the fact that in such cases all energy flows and storages have been accounted for; the total system (plant, exosystem, fields) does not lose energy. Important special cases and applications of the dissipation inequality will be discussed below.

We next present the infinitesimal version of the dissipation inequality (19) in the following theorem. Recall that in quantum mechanics an *observable* is represented as a self-adjoint operator.

Theorem 3.1: The plant \mathbf{P} is *dissipative* with supply rate r with respect to a class \mathcal{W} of exosystems if and only if there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ such that

$$\mathcal{G}_{\mathbf{P} \wedge \mathbf{W}}(V) - r(\mathbf{W}) \leq 0 \quad (20)$$

for all exosystem parameters $\mathbf{W} \in \mathcal{W}$.

Proof: Assume \mathbf{P} is dissipative as stated, and select any exosystem $\mathbf{W} \in \mathcal{W}$ and consider the plant-exosystem network $\mathbf{P} \wedge \mathbf{W}$. Now apply (9) to the network to obtain

$$\frac{d}{dt} \mathbb{E}_0[V(t)]|_{t=0} = \mathcal{G}_{\mathbf{P} \wedge \mathbf{W}}(V). \quad (21)$$

Now combine this with (19) to obtain (20). The converse follows by reversing this argument and integration. ■

Note that all operators appearing in (20) belong to the algebra $\mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{ex}$, since the noise has been averaged out by \mathbb{E}_0 .

Theorem 3.1 is quite general, and contains within it many special cases of interest, e.g. versions of the Bounded and Positive Real Lemmas. See Remark 3.3 and Theorems 3.10 and 3.11.

Remark 3.2: (Non-autonomous case.) For non-autonomous situations, the plant and exosystem operators may depend on time (they can even be random provided they are adapted), and the dissipation inequalities take the forms

$$\mathbb{E}_s \left[V(t) - V(s) - \int_s^t r(\mathbf{W})(r) dr \right] \leq 0 \quad (22)$$

for all $t \geq s$ and all exosystems $\mathbf{W} \in \mathcal{W}$, and

$$\mathcal{G}_{\mathbf{P} \wedge \mathbf{W}}(V)(t) - r(\mathbf{W})(t) \leq 0 \quad (23)$$

for all $t \geq 0$ and all exosystem parameters $\mathbf{W} \in \mathcal{W}$. \square

In what follows, for the sake of clarity, we will be specific about the type of interconnection between the plant and exosystems. In fact we will henceforth assume, unless otherwise stated,

$$\mathbf{P} \wedge \mathbf{W} = \mathbf{P} \triangleleft \mathbf{W}. \quad (24)$$

So in this case, by (16), inequality (20) can be expressed as

$$\begin{aligned} & \mathcal{G}_{\mathbf{P} \triangleleft \mathbf{W}}(V) - r(\mathbf{W}) \\ &= \mathcal{L}_{\mathbf{w}}(X) + \mathcal{L}_{\mathbf{L}}(X) + \mathbf{w}^\dagger (\mathbf{S}^\dagger X \mathbf{S} - X) \mathbf{w} + \mathbf{w}^\dagger \mathbf{S}^\dagger [X, \mathbf{L}] + [\mathbf{L}^\dagger, X] \mathbf{S} \mathbf{w} - i[X, H + D] - r(\mathbf{W}) \leq 0. \end{aligned} \quad (25)$$

Development of the theory below for the more general situation described earlier follows in a straightforward manner using the concepts and network methodology presented here.

Remark 3.3: (Classical deterministic case.) Consider the classical deterministic open system (see [27], [26])

$$\begin{aligned} \dot{x} &= f(x) + g(x)w \\ z &= h(x), \end{aligned} \quad (26)$$

where $x \in \mathbb{R}^n$, $w \in L_{loc}^2([0, \infty), W)$, $W \subset \mathbb{R}$, f and g are smooth vector fields, and h is a smooth real-valued function. This system is dissipative with respect to a supply rate $r(w, z)$ if there exists a non-negative function (the storage function) such that

$$V(x(t)) - V(x(0)) - \int_0^t r(w(s), z(s)) ds \leq 0 \quad (27)$$

for all $w \in L^2[0, t]$ and all $t \geq 0$. The infinitesimal version of this dissipation inequality is

$$\sup_{w \in W} \{ [f(x) + g(x)w]^T \nabla V(x) - r(w, h(x)) \} \leq 0. \quad (28)$$

This is a special case of the quantum formulation given above. To see this, we represent the classical open system as a commutative subsystem of a quantum open system \mathbf{P} with an associated (non-autonomous) exosystem class \mathcal{W} . As in [11, Appendix B], we take the underlying Hilbert space of the classical system to be $\mathfrak{h} = L^2(\mathbb{R}^n)$ with q^j , p_j being the usual canonical position and momentum observables: $q^j \psi(x) = x^j \psi(x)$ and $p_j \psi(x) = -i \partial_j \psi(x)$. We write $q = (q^1, \dots, q^n)^T$, $p = (p_1, \dots, p_n)^T$, and $\nabla = (\partial_1, \dots, \partial_n)^T$, and define Hamiltonians

$$H_f = \frac{1}{2} (f^T p + p^T f), \quad H_g = \frac{1}{2} (g^T p + p^T g). \quad (29)$$

Now if $\varphi = \varphi(q)$ is a function only of the position variables, then

$$-i[\varphi, H_f + H_g w] = [f + gw]^T \nabla \varphi. \quad (30)$$

Hence the classical open system can be described by $\mathbf{P} \boxplus \mathbf{W}$, where

$$\begin{aligned} \mathbf{P} &= (-, -, H_f), \\ \mathbf{W} &\in \mathcal{W} = \{ \mathbf{W} = (-, -, H_g w) : w \in L_{loc}^2([0, \infty), W) \}, \end{aligned} \quad (31)$$

and supply rate

$$r(\mathbf{W}) = r(h, w). \quad (32)$$

The classical deterministic dissipation inequality (28) now follows from (20). \square

Remark 3.4: (Classical stochastic case.) We may extend Remark 3.3 in the following way (cf. [6], [5]). In addition to the signal w we may also consider noise. Equation (26) may be replaced by the stochastic differential equation

$$dx = f(x) dt + g(x) [w dt + dB]$$

where B is a Wiener process. We exploit the fact that the classical Wiener process can be modeled as $B(t) = A(t) + A^*(t)$ with the specification of the Fock vacuum state. To this end, we represent the open system as $\mathbf{P} \triangleleft \mathbf{W}$, where

$$\mathbf{P} = (1, 0, H_f), \quad \mathbf{W} = (1, H_g, w H_g),$$

and H_g is as in (29) above. We note that the Lindblad generator for the term H_g reduces to $-\frac{1}{2} [[X, H_g], H_g]$ on account of the self-adjointness of H_g . Again restricting our interest to functions of the observable q only, we find that $\mathcal{L}_{H_g}(\varphi(q)) \equiv (\mathcal{F}\varphi)(q)$ where we introduce the differential operator

$$\mathcal{F} = \frac{1}{2} g(x)^T \nabla \left(g(x)^T \nabla \right) = \frac{1}{2} g^i(x) g^j(x) \frac{\partial^2}{\partial x^i \partial x^j} + \frac{1}{2} g^i(x) \frac{\partial g^j(x)}{\partial x^i} \frac{\partial}{\partial x^j}.$$

We then find that $\frac{d}{dt} \mathbb{E}_0[\varphi(q(t))] |_{t=0} = [[f + gw]^T \nabla + \mathcal{F}] \varphi(q)$ and the infinitesimal form of the dissipation inequality modifies from (28) to

$$\sup_{w \in W} \left\{ [[f + gw]^T \nabla + \mathcal{F}] \varphi(x) - r(w, h(x)) \right\} \leq 0.$$

Note that the supply rate may include an additive constant term, cf. [6, eq. (2.13)], [5, eq. (10)]. \square

B. Some Properties

In general we can expect physical systems to be dissipative in some sense, and indeed we characterize this precisely in the next theorem. In what follows we denote by \mathscr{W}_u the class of exosystems without any particular constraints (unrestricted).

Theorem 3.5: Let $\mathbf{P} = (\mathbf{S}, \mathbf{L}, H)$ be a plant, and assume there exists an observable $V_0 \geq 0$ commuting with H . Then \mathbf{P} is lossless (hence dissipative) with respect to \mathscr{W}_u for a supply rate $r = r_0$ given by

$$r_0(\mathbf{W}) = \mathcal{G}_{\mathbf{P} \triangleleft \mathbf{W}}(V_0), \quad (33)$$

with storage function $V = V_0$.

This simple (but important!) result follows from a calculation similar to that used to prove Theorem 3.1.

Dissipation properties for reducible networks can be analyzed by considering how the network is constructed in terms of concatenation and series products, and knowledge of how dissipation “transforms” under these products. This is the purpose of the next result; cf. [27, sec. 4].

Lemma 3.6: Let \mathbf{P}_1 and \mathbf{P}_2 be dissipative with respect to supply rates $r_{\mathbf{P}_1}(\mathbf{W})$ and $r_{\mathbf{P}_2}(\mathbf{W})$, storage functions V_1 and V_2 , and exosystem classes \mathscr{W}_1 and \mathscr{W}_2 respectively. Then:

- 1) The concatenated system $\mathbf{P}_1 \boxplus \mathbf{P}_2$ is dissipative with storage function $V_1 + V_2$ and supply rate

$$r_{\mathbf{P}_1 \boxplus \mathbf{P}_2}(\mathbf{W}_1 \boxplus \mathbf{W}_2) = r_{\mathbf{P}_1}(\mathbf{W}_1) + r_{\mathbf{P}_2}(\mathbf{W}_2) + \mathcal{G}_{\mathbf{P}_1 \triangleleft \mathbf{W}_1}(V_2) + \mathcal{G}_{\mathbf{P}_2 \triangleleft \mathbf{W}_2}(V_1), \quad (34)$$

with respect to $\mathscr{W} = \mathscr{W}_1 \boxplus \mathscr{W}_2$. If in addition $\mathcal{A}_{\mathbf{P}_1}$ and $\mathcal{A}_{\mathbf{P}_2}$ commute, then the supply rate simplifies to

$$r_{\mathbf{P}_1 \boxplus \mathbf{P}_2}(\mathbf{W}_1 \boxplus \mathbf{W}_2) = r_{\mathbf{P}_1}(\mathbf{W}_1) + r_{\mathbf{P}_2}(\mathbf{W}_2) + \mathcal{L}_{\mathbf{w}_1}(V_2) + \mathcal{L}_{\mathbf{w}_2}(V_1). \quad (35)$$

If also $\mathcal{A}_{\mathbf{P}_j}$ commutes with \mathscr{W}_k , $j, k \in \{1, 2\}, j \neq k$, then the supply rate is simply $r_{\mathbf{P}_1}(\mathbf{W}_1) + r_{\mathbf{P}_2}(\mathbf{W}_2)$.

- 2) The series system $\mathbf{P}_2 \triangleleft \mathbf{P}_1$ is dissipative with storage function $V_1 + V_2$ and supply rate

$$r_{\mathbf{P}_2 \triangleleft \mathbf{P}_1}(\mathbf{W}) = r_{\mathbf{P}_1}(\mathbf{P}'_2 \triangleleft \mathbf{W}) + r_{\mathbf{P}_2}(\mathbf{P}_1 \triangleleft \mathbf{W}), \quad (36)$$

with respect to the exosystem class

$$\mathscr{W} = \{\mathbf{W} : \mathbf{P}'_2 \triangleleft \mathbf{W} \in \mathscr{W}_1 \text{ and } \mathbf{P}_1 \triangleleft \mathbf{W} \in \mathscr{W}_2\}, \quad (37)$$

where

$$\mathbf{P}'_2 = (\mathbf{S}_1^\dagger \mathbf{S}_2 \mathbf{S}_1, \mathbf{S}_1^\dagger (\mathbf{S}_2 - \mathbf{1}) \mathbf{L}_1 + \mathbf{S}_1^\dagger \mathbf{L}_2, H_2 + \text{Im} \{ \mathbf{L}_2^\dagger (\mathbf{S}_2 + \mathbf{1}) \mathbf{L}_1 - \mathbf{L}_1^\dagger \mathbf{S}_2 \mathbf{L}_1 \}). \quad (38)$$

Proof: For part 1, we have

$$\begin{aligned} \mathcal{G}_{(\mathbf{P}_1 \boxplus \mathbf{P}_2) \triangleleft (\mathbf{W}_1 \boxplus \mathbf{W}_2)}(V_1 + V_2) &= \mathcal{G}_{(\mathbf{P}_1 \triangleleft \mathbf{W}_1) \boxplus (\mathbf{P}_2 \triangleleft \mathbf{W}_2)}(V_1 + V_2) \\ &= \mathcal{G}_{\mathbf{P}_1 \triangleleft \mathbf{W}_1}(V_1) + \mathcal{G}_{\mathbf{P}_2 \triangleleft \mathbf{W}_2}(V_2) + \mathcal{G}_{\mathbf{P}_1 \triangleleft \mathbf{W}_1}(V_2) + \mathcal{G}_{\mathbf{P}_2 \triangleleft \mathbf{W}_2}(V_1) \\ &\leq r_{\mathbf{P}_1}(\mathbf{W}_1) + r_{\mathbf{P}_2}(\mathbf{W}_2) + \mathcal{G}_{\mathbf{P}_1 \triangleleft \mathbf{W}_1}(V_2) + \mathcal{G}_{\mathbf{P}_2 \triangleleft \mathbf{W}_2}(V_1), \end{aligned}$$

so that the last line is a supply rate for the concatenated system.

Similarly, for part 2 we have

$$\begin{aligned} \mathcal{G}_{\mathbf{P}_2 \triangleleft \mathbf{P}_1 \triangleleft \mathbf{W}}(V_1 + V_2) &= \mathcal{G}_{\mathbf{P}_2 \triangleleft \mathbf{P}_1 \triangleleft \mathbf{W}}(V_1) + \mathcal{G}_{\mathbf{P}_2 \triangleleft \mathbf{P}_1 \triangleleft \mathbf{W}}(V_2) \\ &= \mathcal{G}_{\mathbf{P}_1 \triangleleft (\mathbf{P}'_2 \triangleleft \mathbf{W})}(V_1) + \mathcal{G}_{\mathbf{P}_2 \triangleleft (\mathbf{P}_1 \triangleleft \mathbf{W})}(V_2) \\ &\leq r_{\mathbf{P}_1}(\mathbf{P}'_2 \triangleleft \mathbf{W}) + r_{\mathbf{P}_2}(\mathbf{P}_1 \triangleleft \mathbf{W}) \end{aligned}$$

where $\mathbf{P}_2 \triangleleft \mathbf{P}_1 = \mathbf{P}_1 \triangleleft \mathbf{P}'_2$ by [11, Theorem 3.4], with \mathbf{P}'_2 given by (38). ■

We next show that the scattering matrix \mathbf{S} for the plant can be moved into the supply rate.

Lemma 3.7: Let \mathscr{W} be a class of exosystems satisfying

$$\mathbf{W} \in \mathscr{W} \text{ implies } (\mathbf{S}, 0, 0) \triangleleft \mathbf{W} \text{ and } (\mathbf{S}^\dagger, 0, 0) \triangleleft \mathbf{W} \in \mathscr{W}. \quad (39)$$

Then the plant $\mathbf{P} = (\mathbf{S}, \mathbf{L}, H)$ is dissipative with supply rate $r(\mathbf{W})$ with respect to \mathscr{W} if and only if the plant $\mathbf{P}' = (\mathbf{1}, \mathbf{L}, H)$ is dissipative with supply rate $r'(\mathbf{W}) = r((\mathbf{S}^\dagger, 0, 0) \triangleleft \mathbf{W})$ with respect to \mathscr{W} .

Proof: First observe that, using (11),

$$\mathbf{P} \triangleleft \mathbf{W} = \mathbf{P}' \triangleleft (\mathbf{S}, 0, 0) \triangleleft \mathbf{W} = \mathbf{P}' \triangleleft \mathbf{W}'$$

for $\mathbf{P}' = (\mathbf{1}, \mathbf{L}, H)$, $\mathbf{W}' = (\mathbf{S}, 0, 0) \triangleleft \mathbf{W}$, and since \mathbf{S} is unitary, we have $\mathbf{W} = (\mathbf{S}^\dagger, 0, 0) \triangleleft \mathbf{W}'$.

Assume $\mathbf{P} = (\mathbf{S}, \mathbf{L}, H)$ is dissipative with supply rate $r(\mathbf{W})$ with respect to \mathscr{W} . Select any $\mathbf{W}' \in \mathscr{W}$, and set $\mathbf{W} = (\mathbf{S}^\dagger, 0, 0) \triangleleft \mathbf{W}' \in \mathscr{W}$ by (39). Then by Theorem 3.1 inequality (20) holds. Now hence (20) implies

$$\mathcal{G}_{\mathbf{P}' \triangleleft \mathbf{W}'}(V) - r((\mathbf{S}^\dagger, 0, 0) \triangleleft \mathbf{W}') = \mathcal{G}_{\mathbf{P} \triangleleft \mathbf{W}}(V) - r(\mathbf{W}) \leq 0.$$

Therefore $\mathbf{P}' = (\mathbf{1}, \mathbf{L}, H)$ is dissipative with supply rate $r'(\mathbf{W}') = r((\mathbf{S}^\dagger, 0, 0) \triangleleft \mathbf{W}')$ with respect to \mathscr{W} . The converse follows similarly. ■

In view of this result, we shall henceforth assume that the class of exosystems \mathscr{W} satisfies (39), and unless otherwise specified, we consider plants of the form $\mathbf{P} = (\mathbf{1}, \mathbf{L}, H)$ and absorb any scattering matrix into the definition of the supply rate.

It is of interest to interpret the supply rate $r_0(\mathbf{W})$ given by (33) when D has the form

$$D = -i(\mathbf{v}^\dagger \mathbf{K} - \mathbf{K}^\dagger \mathbf{v}), \quad (40)$$

where $\mathbf{K} \in \mathscr{A}_{\mathbf{P}}$ is fixed and \mathbf{v} commutes with $\mathscr{A}_{\mathbf{P}}$. From (16), we can write

$$\begin{aligned} r_0(\mathbf{W}) &= r_0(\mathbf{w}, \mathbf{v}) = \mathcal{L}_{\mathbf{w}}(V_0) + \mathcal{L}_{\mathbf{L}}(V_0) + \mathbf{w}^\dagger [V_0, \mathbf{L}] + [\mathbf{L}^\dagger, V_0] \mathbf{w} - i[V_0, D] \\ &= \mathcal{L}_{\mathbf{w}}(V_0) + \mathcal{L}_{\mathbf{L}}(V_0) + \begin{pmatrix} \mathbf{w}^\dagger & \mathbf{v}^\dagger \end{pmatrix} [V_0, \begin{pmatrix} \mathbf{L} \\ \mathbf{K} \end{pmatrix}] + [(\mathbf{L}^\dagger \quad \mathbf{K}^\dagger), V_0] \begin{pmatrix} \mathbf{w} \\ \mathbf{v} \end{pmatrix} \\ &= \mathcal{L}_{\mathbf{w}}(V_0) + \mathcal{L}_{\mathbf{L}}(V_0) + \begin{pmatrix} \mathbf{w}^\dagger & \mathbf{v}^\dagger \end{pmatrix} \mathbf{Z} + \mathbf{Z}^\dagger \begin{pmatrix} \mathbf{w} \\ \mathbf{v} \end{pmatrix}, \end{aligned} \quad (41)$$

where

$$\mathbf{Z} = [V_0, \begin{pmatrix} \mathbf{L} \\ \mathbf{K} \end{pmatrix}].$$

If we think of \mathbf{Z} as an “output” quantity, then the last two terms correspond to a product of input and output terms, i.e. an energy flow into the plant from the exosystem—these terms capture the *passivity* of the plant. The term $\mathcal{L}_{\mathbf{L}}(V_0)$ is known in quantum physics as a “dissipation” or “damping” term, which in the model arises from the quantum noise in the field; when negative, this term represents energy lost from the plant to the field (heat bath). The first term, $\mathcal{L}_{\mathbf{w}}(V_0)$, arises from a “*dt*” or “signal” term in the field inputs, and is in general zero when \mathbf{w} commutes with plant operators; it is an exosystem partner to the field dissipation term. When the sum of these terms is negative, then one has a stronger form of passivity (cf. strictly passive classical systems, see, e.g. [26, Chapter 3]).

C. Stability

In the case of classical deterministic systems, dissipativity plays an important role in stability analysis, [27], [13]. For instance, strictly passive systems, mentioned above, are asymptotically stable. The purpose of this section is to make this connection in our current quantum context using a simple exponential stability criterion, given in the following lemma.

Lemma 3.8: Let \mathbf{P} be a plant for which there exists a non-negative observable V satisfying the differential inequality

$$\mathcal{G}_{\mathbf{P}}(V) + cV \leq 0, \quad (42)$$

where $c > 0$ is a real number. Then for any state ρ on $\mathscr{A}_{\mathbf{P}}$, we have³

$$\langle \rho, \mathbb{E}_0[V(t)] \rangle \leq e^{-ct} \langle \rho, V \rangle \quad (43)$$

and so $\lim_{t \rightarrow \infty} \langle \rho, \mathbb{E}_0[V(t)] \rangle = 0$.

Proof: Integrating the plant dynamics we find that

$$\mathbb{E}_t \left[V(t+h) - V(t) - c \int_t^{t+h} V(r) dr \right] \leq 0, \quad h \geq 0. \quad (44)$$

Now from [23, sec. 26], we have $\mathbb{E}_0 \mathbb{E}_t = \mathbb{E}_0$ for $t \geq 0$, hence it follows that the expectation $\langle V(t) \rangle = \langle \rho, \mathbb{E}_0[V(t)] \rangle$ satisfies

$$\langle V(t+h) \rangle - \langle V(t) \rangle - c \int_t^{t+h} \langle V(r) \rangle dr \leq 0, \quad h \geq 0. \quad (45)$$

From this we deduce

$$\frac{d}{dt} \langle V(t) \rangle \leq -c \langle V(t) \rangle. \quad (46)$$

The assertions of the lemma now follow. ■

We now state the strictly passive stability result for quantum systems.

Theorem 3.9: Let \mathbf{P} be dissipative with storage function V and supply rate $r(\mathbf{W})$. Assume that the supply rate satisfies

$$r((\mathbf{I}, 0, 0)) \leq -cV \quad (47)$$

for some real number $c > 0$. Then for the unperturbed plant $\mathbf{P} = \mathbf{P} \triangleleft (\mathbf{I}, 0, 0)$ we have $\lim_{t \rightarrow \infty} \langle \rho, \mathbb{E}_0[V(t)] \rangle = 0$ for any state ρ on $\mathscr{A}_{\mathbf{P}}$.

This result follows, of course, from Lemma 3.8 and Theorem 3.1. It is possible to consider more general stability results and this will be taken up in future work.

³The notation $\langle A \rangle = \langle \rho, A \rangle$ means the quantum expectation of an operator A with respect to a state ρ .

D. Special Cases

In this subsection we discuss some special cases of importance. To help make the ideas clearer, we will assume that the exosystems commute with the plant. More general results can be formulated using the framework presented above.

Consider a plant $\mathbf{P} = (\mathbf{1}, \mathbf{L}, H)$, and let $F, \mathbf{N}, \mathbf{Z} \in \mathcal{A}_{\mathbf{P}}$, with F self-adjoint. Define a class of exosystems

$$\mathcal{W}_1 = \left\{ \mathbf{W} = (\mathbf{R}, \mathbf{w}, -i(\mathbf{v}^\dagger \mathbf{K} - \mathbf{K}^\dagger \mathbf{v})) : \mathbf{K} \in \mathcal{A}_{\mathbf{P}} \text{ is fixed and } \mathbf{w}, \mathbf{v} \text{ commute with } \mathcal{A}_{\mathbf{P}} \right\}.$$

We say that \mathbf{P} is *passive* (with respect to \mathcal{W}_1) if it is dissipative with respect to the supply rate

$$r(\mathbf{W}) = r(\mathbf{w}, \mathbf{v}) = -\mathbf{N}^\dagger \mathbf{N} + \begin{pmatrix} \mathbf{w}^\dagger & \mathbf{v}^\dagger \end{pmatrix} \mathbf{Z} + \mathbf{Z}^\dagger \begin{pmatrix} \mathbf{w} \\ \mathbf{v} \end{pmatrix} + \lambda \quad (48)$$

for some non-negative real number λ , and class \mathcal{W}_1 . Explicitly, this means that \mathbf{P} is passive if there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ and a non-negative real number λ such that

$$\mathbb{E}_0 \left[V(t) - V - \int_0^t \left(\begin{pmatrix} \mathbf{w}^\dagger(s) \\ \mathbf{v}^\dagger(s) \end{pmatrix} \mathbf{Z}(s) + \mathbf{Z}^\dagger(s) \begin{pmatrix} \mathbf{w}(s) \\ \mathbf{v}(s) \end{pmatrix} - \mathbf{N}^\dagger(s) \mathbf{N}(s) \right) ds \right] - \lambda t \leq 0 \quad (49)$$

for all exosystems $\mathbf{W} \in \mathcal{W}_1$ and all $t \geq 0$.

Theorem 3.10: (Positive Real Lemma) A plant $\mathbf{P} = (\mathbf{1}, \mathbf{L}, H)$ is passive (with respect to \mathcal{W}_1) if and only if there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ and a non-negative real number λ such that

$$\mathcal{L}_{\mathbf{L}}(V) - i[V, H] + \mathbf{N}^\dagger \mathbf{N} - \lambda \leq 0, \quad (50)$$

$$\mathbf{Z} = [V, \begin{pmatrix} \mathbf{L} \\ \mathbf{K} \end{pmatrix}]. \quad (51)$$

Proof: We use some results from the Appendix in what follows. If \mathbf{P} is passive, there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ and a non-negative real number λ such that

$$\mathcal{L}_{\mathbf{L}}(V) - i[V, H] + \begin{pmatrix} \mathbf{w}^\dagger \\ \mathbf{v}^\dagger \end{pmatrix} ([V, \mathbf{L}] - \mathbf{Z}) + ([\mathbf{L}^\dagger, V] - \mathbf{Z}^\dagger) \begin{pmatrix} \mathbf{w} \\ \mathbf{v} \end{pmatrix} + \mathbf{N}^\dagger \mathbf{N} - \lambda \leq 0 \quad (52)$$

for all exosystem parameters $\mathbf{W} = (\mathbf{R}, \mathbf{w}, -i(\mathbf{v}^\dagger \mathbf{K} - \mathbf{K}^\dagger \mathbf{v})) \in \mathcal{W}_1$. Setting $\mathbf{w} = 0$ and $\mathbf{v} = 0$ we obtain (50). Now let \mathbf{w} vary freely but commuting with plant operators to deduce (51). ■

The Bounded Real Lemma is used to determine the L^2 gain of a system, and in conjunction with the Small Gain Theorem, can be used for robust stability analysis and design, [12], [35], [3]. Again consider a plant $\mathbf{P} = (\mathbf{1}, \mathbf{L}, H)$, let $\mathbf{N}, \mathbf{Z} \in \mathcal{A}_{\mathbf{P}}$, and let $g > 0$ be a real number (gain parameter). In order to simplify the exposition, we restrict our attention to the class

$$\mathcal{W}_2 = \{ \mathbf{W} = (\mathbf{R}, \mathbf{w}, 0) : \mathbf{w} \text{ commutes with } \mathcal{A}_{\mathbf{P}} \}.$$

We say that \mathbf{P} has *gain* g (with respect to \mathcal{W}_2) if it is dissipative with respect to the supply rate

$$r(\mathbf{W}) = g^2 \mathbf{w}^\dagger \mathbf{w} - (\mathbf{N} + \mathbf{Z}\mathbf{w})^\dagger (\mathbf{N} + \mathbf{Z}\mathbf{w}) + \lambda, \quad (53)$$

for a real number $\lambda \geq 0$, and class \mathcal{W}_2 ; i.e. there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ and a non-negative real number λ such that

$$\mathbb{E}_0 \left[V(t) - V - \int_0^t (g^2 \mathbf{w}^\dagger(s) \mathbf{w}(s) - (\mathbf{N}(s) + \mathbf{Z}(s) \mathbf{w}(s))^\dagger (\mathbf{N}(s) + \mathbf{Z}(s) \mathbf{w}(s))) ds \right] - \lambda t \leq 0 \quad (54)$$

for all exosystems $\mathbf{W} \in \mathcal{W}_2$ and all $t \geq 0$.

Theorem 3.11: (Bounded Real Lemma) A plant $\mathbf{P} = (\mathbf{1}, \mathbf{L}, H)$ has gain g (with respect to \mathcal{W}_2) if and only if there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ and a non-negative real number λ such that

$$\mathbf{\Gamma} = g^2 - \mathbf{Z}^\dagger \mathbf{Z} \geq 0 \quad (55)$$

and

$$\mathcal{L}_{\mathbf{L}}(V) - i[V, H] - \mathbf{w}^\dagger \mathbf{\Gamma} \mathbf{w} + \mathbf{w}^\dagger ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N}) + ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N})^\dagger \mathbf{w} + \mathbf{N}^\dagger \mathbf{N} - \lambda \leq 0 \quad (56)$$

for all exosystem parameters \mathbf{w} . If $\mathbf{\Gamma}^{-1}$ exists, then $\mathbf{P} = (\mathbf{1}, \mathbf{L}, H)$ has gain g (with respect to \mathcal{W}_2) if

$$\mathcal{L}_{\mathbf{L}}(V) - i[V, H] + \mathbf{N}^\dagger \mathbf{N} + ([\mathbf{L}^\dagger, V] + \mathbf{N}^\dagger \mathbf{Z}) \mathbf{\Gamma}^{-1} ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N}) - \lambda \leq 0. \quad (57)$$

Proof: If \mathbf{P} has gain g , then there exists a non-negative system observable $V \in \mathcal{A}_{\mathbf{P}}$ and a real number $\lambda \geq 0$ such that

$$\mathcal{L}_{\mathbf{L}}(V) - i[V, H] - \mathbf{w}^\dagger \mathbf{\Gamma} \mathbf{w} + \mathbf{w}^\dagger ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N}) + ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N})^\dagger \mathbf{w} + \mathbf{N}^\dagger \mathbf{N} - \lambda \leq 0 \quad (58)$$

for all exosystem parameters \mathbf{w} . From the Appendix we see that $\mathbf{\Gamma} \geq 0$, hence (55). In equality (56) also follows.

Next, if Γ^{-1} exists, define

$$\mathbf{w}^* = \Gamma^{-1}([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N}). \quad (59)$$

Then by completion of squares

$$\begin{aligned} & -\mathbf{w}^\dagger \Gamma \mathbf{w} + \mathbf{w}^\dagger ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N}) + ([\mathbf{L}^\dagger, V] + \mathbf{N}^\dagger \mathbf{Z}) \mathbf{w} \\ &= ([\mathbf{L}^\dagger, V] + \mathbf{N}^\dagger \mathbf{Z}) \Gamma^{-1} ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N}) - (\mathbf{w} - \mathbf{w}^*)^\dagger \Gamma (\mathbf{w} - \mathbf{w}^*) \\ &\leq ([\mathbf{L}^\dagger, V] + \mathbf{N}^\dagger \mathbf{Z}) \Gamma^{-1} ([V, \mathbf{L}] + \mathbf{Z}^\dagger \mathbf{N}). \end{aligned}$$

This inequality and (57) imply (56) as required. \blacksquare

Remark 3.12: Note that the ‘‘optimal’’ exosystem parameter \mathbf{w}^* defined by (59) belongs to $\mathcal{A}_{\mathbf{P}}$, and so does not in general commute with $\mathcal{A}_{\mathbf{P}}$, and consequently lies outside the class of exosystems under consideration; i.e., $\mathbf{w}^* \notin \mathcal{W}_2$ in general. \square

E. Uncertainty Modeling

Because of its importance to questions of robustness, in this subsection we briefly discuss how uncertainty can be modeled in the framework of this paper. However, a detailed treatment of robustness is beyond the scope of the present paper.

Consider a plant $\mathbf{P} = (\mathbf{I}, \mathbf{L}, H)$, where

$$\mathbf{L} = (1 + \epsilon)\mathbf{L}_0, \quad H = H_0 + D. \quad (60)$$

Here ϵ is a real parameter. Then using (11) we can write

$$\mathbf{P} = \mathbf{P}_0 \triangleleft \mathbf{W} = (\mathbf{I}, \mathbf{L}_0, H) \triangleleft (\mathbf{I}, (\epsilon^2 + 2\epsilon)\mathbf{L}_0, D), \quad (61)$$

which represents the plant \mathbf{P} as a nominal system \mathbf{P}_0 with the uncertainty connected into it from an exosystem \mathbf{W} containing the uncertainty terms.

More generally, one could contemplate uncertainty models of the form $\mathbf{P} = \mathbf{P}_0 \wedge \mathbf{W}$ for a suitable class of exosystems and interconnection structure. Such uncertainty descriptions can be more general than the parametric uncertainty we have considered in this subsection.

F. Examples

We now give some simple examples which illustrate the dissipative nature of open quantum systems. The first example is a damped harmonic oscillator, which is a widely-used model for an optical cavity.

Example 3.13: (Damped oscillator) Consider an open harmonic oscillator

$$\mathbf{P} = (1, \sqrt{\gamma}a, \omega a^*a),$$

where a is the annihilation operator, γ is a coupling parameter, and ω is a frequency parameter. Let $V_0 = H/\omega = a^*a$. By Ito’s rule (5) we have, for an arbitrary exosystem $\mathbf{W} = (R, w, D) \in \mathcal{W}_u$

$$\mathcal{G}_{\mathbf{P} \triangleleft \mathbf{W}}(V_0) = -\gamma a^*a - \sqrt{\gamma}(w^*a + a^*w) + \mathcal{L}_w(V_0) - i[V_0, D], \quad (62)$$

from which we see that this plant is lossless with supply rate

$$r_0(\mathbf{W}) = -\gamma a^*a - \sqrt{\gamma}(w^*a + a^*w) + \mathcal{L}_w(V_0) - i[V_0, D]. \quad (63)$$

Hence this system is passive with output $Z = [V_0, L] = -\sqrt{\gamma}a$, $\lambda = 0$ and storage function $V_0 = H/\omega = a^*a$. When $D = 0$ and $\mathbf{W} = (1, 0, 0)$ the expected value of $V_0(t)$ tends to zero (asymptotically stable) as the plant loses energy to the field (Theorem 3.9).

Now by completion of squares the supply rate can be re-written

$$r_0(\mathbf{W}) = -(\sqrt{\gamma}a + w)^*(\sqrt{\gamma}a + w) + w^*w + \mathcal{L}_w(V_0) - i[V_0, D] \quad (64)$$

and hence the system has gain 1 relative to the output quantity $\sqrt{\gamma}a + w$ and commuting inputs w .

Note that if we include ground state energy and write $V = a^*a + \frac{1}{2} = q^2 + p^2$ (here $q = a + a^*$, $p = -i(a - a^*)$), then passivity and gain holds but with $\lambda = \gamma > 0$. \square

The second example to follow is also an open harmonic oscillator, but this time it is undamped. Such a model was used in [4] to describe the behavior of an atom trapped in a cavity.

Example 3.14: (Undamped oscillator) Here we consider another open harmonic oscillator

$$\mathbf{P} = (1, \sqrt{\kappa}(a + a^*), \omega a^*a),$$

where a is the annihilation operator, κ is a coupling parameter, and ω is the natural frequency. As above, let $V_0 = H/\omega = a^*a$. By Ito’s rule (5) we have, for an arbitrary exosystem $\mathbf{W} = (R, w, D) \in \mathcal{W}_u$

$$\mathcal{G}_{\mathbf{P} \triangleleft \mathbf{W}}(V_0) = \kappa + \sqrt{\kappa}(w^*(a^* - a) + (a - a^*)w) + \mathcal{L}_w(V_0) - i[V_0, D] \quad (65)$$

Hence we see that this plant is lossless (passive) with supply rate

$$r_0(\mathbf{W}) = \kappa + \sqrt{\kappa}(w^*(a^* - a) + (a - a^*)w) + \mathcal{L}_w(V_0) - i[V_0, D]. \quad (66)$$

In this case when $\mathbf{W} = (1, 0, 0)$ the expected value of $V_0(t)$ will increase at a rate κ . \square

The next example is that of a two-level system often used to model ground and excited states for atoms.

Example 3.15: (Two-level atom) In this example we consider an open two level atom

$$\mathbf{P} = (1, \sqrt{\gamma}\sigma_-, \frac{1}{2}\omega\sigma_z),$$

where $\sigma_x, \sigma_y, \sigma_z$ denote the Pauli matrices (see, e.g. [10, sec. 9.1.1]) and $\sigma_{\pm} = \frac{1}{2}(\sigma_x \pm i\sigma_y)$.

Consider $V_0 = \sigma_1 = \frac{1}{2}(I + \sigma_z) \geq 0$ (here I is the 2×2 identity matrix). By Ito's rule, we find that for an arbitrary exosystem connected in series with the plant $\mathbf{P} \triangleleft \mathbf{W}$

$$\begin{aligned} \mathcal{G}_{\mathbf{P} \triangleleft \mathbf{W}}(\sigma_1) &= -\gamma\sigma_1 - \sqrt{\gamma}(w^*\sigma_- + \sigma_+w) + \mathcal{L}_w(\sigma_1) - i[\sigma_1, D] \\ &= -(\sqrt{\gamma}\sigma_- + w)^*(\sqrt{\gamma}\sigma_- + w) + w^*w + \mathcal{L}_w(\sigma_1) - i[\sigma_1, D]. \end{aligned} \quad (67)$$

Therefore this system is lossless (passive), and has gain 1 with respect to the output quantity $\sqrt{\gamma}\sigma_- + w$ and commuting inputs w . When $D = 0$ and $\mathbf{W} = (1, 0, 0)$ the expected value of $V_0(t) = \sigma_1(t)$ tends to zero (asymptotically stable). \square

The final example of this subsection looks at the effect of parameter uncertainty on the behavior of the damped oscillator.

Example 3.16: (Parameter uncertainty) As an example of this type of uncertainty modeling, consider the plant of Example 3.13, where the values of γ and ω may not be known accurately. This type of uncertainty is common in quantum optics, where γ is a measure of mirror transmissivity and ω corresponds to a detuning of the cavity relative to the input field.

In the notation of subsection III-E, let $L_0 = \sqrt{\gamma_0}a$, $H_0 = 0$ denote the nominal parameters, defining the nominal plant $\mathbf{P}_0 = (1, \sqrt{\gamma_0}a, 0)$, a tuned cavity. Let the true parameters be $L = (1 + \epsilon)\sqrt{\gamma_0}a$, $H = \omega a^*a$, a detuned cavity $\mathbf{P} = (1, (1 + \epsilon)\sqrt{\gamma_0}a, \omega a^*a)$. Hence the uncertain exosystem is $\mathbf{W} = (1, \epsilon\sqrt{\gamma_0}a, \omega a^*a)$ (so that $w = \epsilon\sqrt{\gamma_0}a$ and $D = \omega a^*a$).

Then a straightforward calculation shows that

$$\begin{aligned} \mathcal{G}_{\mathbf{P}}(a^*a) &= \mathcal{G}_{\mathbf{P}_0}(a^*a) - (\epsilon^2 + 2\epsilon)\gamma_0 a^*a \\ &= -(1 + \epsilon)^2 a^*a \leq 0. \end{aligned}$$

This means that the true system is always stable, regardless of the uncertainty, though the decay rate does change. This of course is expected of a passive physical system.

However, other aspects of system performance may be affected. For instance, consider the quadratures $q = a + a^*$, $p = -i(a - a^*)$, which are rotated by the detuning ω . Indeed, if we focus on the observable q^2 , then the uncertain exosystem contribution to the true Lindblad generator is

$$-i[q^2, \omega a^*a] = \omega(qp + pq),$$

which depends on the detuning ω .

We see, therefore, that a detailed robustness analysis with respect to parameter uncertainty involves consideration of one or more observables. \square

IV. FEEDBACK CONTROL DESIGN BY INTERCONNECTION

A. Control Design Formulation

In the previous section we described how the behavior of plant is influenced by exogenous influences (represented as exosystems) using a quantum network framework. We now employ this same framework to consider problems of control system design. The network framework allows us to efficiently express a range of control design problems, and is similar in spirit, but not in detail,⁴ to the behavioral ‘‘control as interconnection’’ viewpoint advocated by Willems and coworkers, [28], [29], [24], [25], [31].

Let \mathbf{P} be a plant which can be interconnected with a controller \mathbf{C} in a network $\mathbf{P} \wedge \mathbf{C}$, as described in subsection II-B. We denote by \mathcal{C} a class of control systems for which such a network is defined. Since the network parameters $\mathbf{P} \wedge \mathbf{C}$ (together with the inputs) determine the dynamical evolution of the plant-controller network, control design can be thought of in terms of shaping the network dynamics in a desired way by appropriate choice of controller $\mathbf{C} \in \mathcal{C}$. Note that this framework is general enough to allow us to consider choices for the controller that are quantum, or classical, or a mixture of the two (cf. [16]).

It is worth remarking that the distinction between plant and controller is not always clear-cut. Indeed, the plant may need to be engineered in an appropriate way to facilitate control. For example, one may desire certain field couplings or direct

⁴The specific technical definition of behavior used in [28] is not applicable in our present open quantum context. In this paper we do not attempt to extend this definition, but rather work directly with system models and interconnections using the quantum network theory.

interaction Hamiltonians to be physically available—this clearly relates to the design of the plant. This issue, of course, is not unknown in classical control engineering, and is evident in the examples discussed in subsection IV-C.

If one is interested in the expected behavior of the network for a range of variables X , then it may be appropriate to work directly with the network Lindblad generator $\mathcal{G}_{\mathbf{P}\wedge\mathbf{C}}(X)$, and use the form of this generator to determine the controller \mathbf{C} , given the objectives. This approach is roughly dual to a method based on master equations already in use, see, e.g. [25].

In what follows we describe a control design procedure that extends classical methods including passivity-based control (PBC), “energy shaping” control, interconnection and damping assignment (IDA) PBC, and, as mentioned above, behavioral “control as interconnection”, [20], [26], [21], [22], [28], [29], [24], [25], [31].

We specify the control objectives by encoding them in a non-negative observable $V_d \in \mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{\mathbf{C}}$ (the parameters of the controllers $\mathbf{C} \in \mathcal{C}$ are assumed to belong to $\mathcal{A}_{\mathbf{C}}$), a supply rate $r_d(\mathbf{W})$, and a class of exosystems \mathcal{W}_d for which a network $(\mathbf{P} \wedge \mathbf{C}) \wedge \mathbf{W}$ is well defined. One then seeks to find, if possible, a controller $\mathbf{C} \in \mathcal{C}$ such that

$$\mathcal{G}_{(\mathbf{P}\wedge\mathbf{C})\wedge\mathbf{W}}(V_d) - r_d(\mathbf{W}) \leq 0 \quad (68)$$

for all exosystem parameters $\mathbf{W} \in \mathcal{W}_d$. In other words, one seeks a controller for which the closed loop system is dissipative with storage function V_d , supply rate $r_d(\mathbf{W})$, and exosystem class \mathcal{W}_d . The exosystems are included to facilitate robust control system design for situations where uncertainty and disturbances are important. The observable V_d is something which on average should be small (such as regulation errors), or tend to zero as time evolves. The supply rate may also contain such “small” quantities, as well as terms from the exosystems. The supply rate need not be the natural supply rate for the network—the inequality in the dissipation inequality can be exploited to permit other choices.

B. Controller Synthesis

We shall now describe how standard problems of stabilization, regulation, and robust control fall within the scope of the controller synthesis framework formulated in the previous subsection. We begin with a general synthesis problem that abstracts stabilization and regulation, since they are closely related. These problems correspond to a choice V_d of a non-negative observable whose expected value we wish to go to zero as time approaches infinity. For definiteness, we choose $r_d(\mathbf{W}) = -cV_d$, where $c > 0$ is a suitable real number, and $\mathcal{W}_d = \{(-, -, 0)\}$, which consists only of the trivial exosystem, so that $(\mathbf{P} \wedge \mathbf{C}) \wedge \mathbf{W} = (\mathbf{P} \wedge \mathbf{C}) \boxplus (-, -, 0) = \mathbf{P} \wedge \mathbf{C}$.

Theorem 4.1: (Stabilization/regulation) If there exists a controller $\mathbf{C} \in \mathcal{C}$ and non-negative observable $V_d \in \mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{\mathbf{C}}$ such that the plant-controller network $\mathbf{P} \wedge \mathbf{C}$ satisfies

$$\mathcal{G}_{\mathbf{P}\wedge\mathbf{C}}(V_d) - cV_d \leq 0 \quad (69)$$

for some real $c > 0$, then $\langle \rho, V_d(t) \rangle \rightarrow 0$ as $t \rightarrow \infty$ exponentially for any state ρ on $\mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{\mathbf{C}}$.

This theorem follows from the stability results give in subsection III-C.

Our next result is a general theorem concerning nonlinear quantum H^∞ robust control, which generalizes the linear quantum results given in [16]. We use an exosystem class $\mathcal{W}_d = \{\mathbf{W} : \mathbf{W} = (\mathbf{I}, \mathbf{w}, 0) : \mathbf{w} \text{ commutes with } \mathcal{A}_{\mathbf{P}}\}$ to describe the “disturbance” inputs. The next theorem is a consequence of a slight extension of the Bounded Real Lemma (Theorem 3.11) applied to the plant-controller network $\mathbf{P} \wedge \mathbf{C}$.

Theorem 4.2: (H^∞ control) If there exists a controller $\mathbf{C} \in \mathcal{C}$ and a non-negative observable $V_d \in \mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{\mathbf{C}}$ such that the plant-controller network $\mathbf{P} \wedge \mathbf{C}$ satisfies

$$g^2 - \mathbf{Z}^\dagger \mathbf{Z} \geq 0 \quad (70)$$

and

$$\mathcal{G}_{(\mathbf{P}\wedge\mathbf{C})\wedge\mathbf{W}}(V_d) - g^2 \mathbf{w}^\dagger \mathbf{w} + (\mathbf{N} + \mathbf{Z}\mathbf{w})^\dagger (\mathbf{N} + \mathbf{Z}\mathbf{w}) - \lambda \leq 0 \quad (71)$$

for some real $g > 0$, $\lambda \geq 0$, and all exosystem parameters $\mathbf{W} \in \mathcal{W}_d$, then the plant-controller network $\mathbf{P} \wedge \mathbf{C}$ has gain g .

C. Examples

Our first design example is a regulation problem analogous to the classical problem of designing a controller to maintain a given value of capacitor charge in a RLC circuit, [21].

Example 4.3: (Regulation) Consider an open harmonic oscillator (damped cavity) $\mathbf{P} = (1, a, 0)$ (recall Example 3.13). If the input field is a vacuum, photons initially in the cavity will eventually leak out. Suppose our control objective is to maintain a given value for the steady state expected photon number. Let’s choose a value α for the desired steady-state value of a , which corresponds to a number $\alpha^* \alpha$ of photons; i.e., we want the cavity to be in a coherent state $|\alpha\rangle$ in the steady-state.

Suppose we simply take the controller to be a system directly coupled to the plant; thus if

$$\mathbf{C} = (1, 0, -i(K_P^* \nu - \nu^* K_P)),$$

where K_P is a plant operator and ν is a complex number, both to be chosen; then the closed loop system is simply

$$\mathbf{P} \wedge \mathbf{C} = \mathbf{P} \boxplus \mathbf{C}.$$

We set

$$V_d = (a - \alpha)^*(a - \alpha) = a^*a - \alpha^*a - a^*\alpha + \alpha^*\alpha,$$

and for a positive real number c ,

$$r_d(\mathbf{W}) = -cV_d,$$

with $\mathscr{W}_d = \{(-, -, 0)\}$, which consists only of the trivial exosystem, as in Theorem 4.1. Note that the expected value of V_d in the state α is zero: $\langle \alpha | V_d | \alpha \rangle = 0$.

The design problem is to select, if possible, K_P , a plant operator, and ν , a complex number, such that

$$\mathcal{G}_{\mathbf{P} \boxplus \mathbf{C}}(V_d) + cV_d \leq 0$$

for suitable $c > 0$. We choose $K_P = a$. Then the LHS of this expression is

$$-a^*a(1 - c) + a\left(\frac{\alpha^*}{2} - \nu^* - c\alpha^*\right) + a^*\left(\frac{\alpha}{2} - \nu - c\alpha\right) + \alpha^*\nu + \alpha\nu^* + c\alpha^*\alpha.$$

If we set $c = 1/2$, $\nu = -\alpha/2$, then this expression equals $-V_d/2$. Therefore

$$\mathcal{G}_{\mathbf{P} \boxplus \mathbf{C}}(V_d) \leq -V_d/2$$

which implies that the expected value of $V_d(t)$ tends to zero as $t \rightarrow \infty$ (by Theorem 3.9), and the control objective is achieved. Note that $\langle \alpha | \mathcal{G}_{\mathbf{P} \boxplus \mathbf{C}}(V_d) | \alpha \rangle = 0$.

Physically, this control design corresponds to a classical energy source connected to the cavity, such as when the vacuum field is replaced by a coherent field (signal plus noise), i.e. a laser beam. \square

Decoherence is a fundamental problem in quantum technology which has attracted considerable attention in the fields of quantum information and computing. The next simple example addresses this problem, and while not meant to provide a general solution to problems caused by decoherence, it does show that fully coherent feedback has some potential to reduce its effects.

Example 4.4: (Decoherence) Consider an open two-level atom (recall Example 3.15), but with two field channels:

$$\mathbf{P} = (1, \sqrt{\gamma_1} \sigma_-, \frac{1}{2} \omega \sigma_z) \boxplus (1, \sqrt{\gamma_2} \sigma_-, 0),$$

where we write $\gamma = \gamma_1 + \gamma_2$. With vacuum inputs, the mean excited state energy $\langle \sigma_1(t) \rangle$ will decay to zero due to the decoherence modeled by the vacuum field couplings. Our control objective here is to reduce or eliminate, if possible, this decoherence decay, so that the atom may maintain its energy.

We use a simple plant-controller network

$$\mathbf{P} \wedge \mathbf{C} = (1, \sqrt{\gamma_2} \sigma_-, 0) \triangleleft \mathbf{C} \triangleleft (1, \sqrt{\gamma_1} \sigma_-, \frac{1}{2} \omega \sigma_z),$$

and set $V_d = \sigma_1$. We choose $r_d(\mathbf{W}) = -cV_d$, with $c \geq 0$ to be chosen as small as possible, and $\mathscr{W}_d = \{(-, -, 0)\}$. Our objective is then

$$\mathcal{G}_{\mathbf{P} \wedge \mathbf{C}}(V_d) + cV_d \leq 0.$$

If we simply set

$$\mathbf{C} = (-1, 0, 0),$$

i.e. a 180° phase shift, then we have

$$\mathcal{G}_{\mathbf{P} \wedge \mathbf{C}}(\sigma_1) = -(\gamma - 2\sqrt{\gamma_1\gamma_2})\sigma_1,$$

so that $c = \gamma - 2\sqrt{\gamma_1\gamma_2} \leq \gamma$. Therefore the energy decay has been reduced, and can be eliminated (in principle) if $\gamma_1 = \gamma_2 = \gamma/2$. This controller simply effects a destructive interference which reduces the energy flowing out. \square

The next example shows that care must be exercised when attempting to use classical control design methods. Difficulties can arise due to the presence of quantum noise and the fact that physical quantities do not in general commute.

Example 4.5: (Stabilization) Suppose we wish to stabilize the plant of Example 3.14, which is not asymptotically stable, using the standard method from classical control theory for stabilizing Hamiltonian systems, [26, sec. 4.1]. We set $D = 0$ to illustrate what happens when one uses field-mediated couplings, and for simplicity $\kappa = 1$. The classical Hamiltonian stabilization procedure is to use negative feedback

$$w = -k(a^* - a). \tag{72}$$

We will explain the physical meaning of this feedback shortly.

Now from (65) with $V_0 = a^*a$, we have

$$\begin{aligned} \mathcal{G}_{\mathbf{P} \triangleleft \mathbf{W}}(V_0)|_{w=-k(a^*-a)} &= 1 - 2k(a - a^*)(a^* - a) + k^2 \\ &= 1 - 2k(2a^*a + 1 - a^2 - (a^*)^2) + k^2 \end{aligned} \quad (73)$$

which is not in general negative, and so stabilization is not assured, in contrast to the classical case.

The physical meaning of the control law (72) is that one is implementing a closed loop system

$$\mathbf{P} \wedge \mathbf{C} = \mathbf{P} \triangleleft (1, -k(a^* - a), 0),$$

which means that it must be physically possible to introduce a field coupling $-k(a^* - a)$ to the system. The controller $\mathbf{C} = (1, -k(a^* - a), 0)$ is simply implementing this coupling.

A preferable method of stabilization for this system would be to introduce a coupling $\sqrt{\gamma}a$, if possible, which would allow the system to loose energy to a heat bath. The plant-controller system in this case is simply

$$\mathbf{P} \wedge \mathbf{C} = \mathbf{P} \boxplus (1, \sqrt{\gamma}a, 0).$$

Other methods like this could also be considered where energy can be lost via a controller, using direct or field-mediated interactions. \square

Linear open quantum systems are those for which the conjugate variables for position and momentum satisfy linear stochastic differential equations. Such systems include many examples in quantum optics. The next example illustrates how the H^∞ synthesis results of [16] fit into the present network design framework by considering one of the examples from that paper, where both the plant and controller are optical cavities.

Example 4.6: (H^∞ robust control, [16, sec. VII-A]) Consider the plant-controller network of Figure 2. The control objective is to reduce the gain from input w to output z by an appropriate choice of controller \mathbf{C} .




Fig. 2. A plant-controller network for H^∞ control.

The plant is a cavity with annihilation operator a and three mirrors (three field channels)

$$\begin{aligned} \mathbf{P} &= \mathbf{P}_1 \boxplus \mathbf{P}_2 \boxplus \mathbf{P}_3 \\ &= (1, \sqrt{\kappa_1}a, 0) \boxplus (1, \sqrt{\kappa_2}a, 0) \boxplus (1, \sqrt{\kappa_3}a, 0), \end{aligned}$$

and the controller is assumed to have the form

$$\mathbf{C} = \mathbf{C}_1 \boxplus \mathbf{C}_2 \boxplus \mathbf{C}_3.$$

The plant-controller network is

$$\mathbf{P} \wedge \mathbf{C} = \mathbf{P}_1 \boxplus (\mathbf{C}_3 \triangleleft \mathbf{P}_2) \boxplus (\mathbf{P}_3 \triangleleft \mathbf{C}_1) \boxplus \mathbf{C}_2.$$

The supply rate is

$$r(\mathbf{W}) = g^2 w^* w - (\sqrt{\kappa_3}a + w)^* (\sqrt{\kappa_3}a + w)$$

for exosystems $\mathbf{W} \in \mathcal{W}_d$, where

$$\mathcal{W}_d = \{ \mathbf{W} = (1, 0, 0) \boxplus (1, w, 0) \boxplus (1, 0, 0) \boxplus (1, 0, 0) : w \text{ commutes with } \mathcal{A}_{\mathbf{P}} \otimes \mathcal{A}_{\mathbf{C}} \}.$$

The control objective is now in the form (68).

For the plant parameters $\kappa_1 = 2.6$, $\kappa_2 = 0.2$, $\kappa_3 = 0.2$, a controller was found in [16, sec. VII-A] for a gain value of $g = 0.1$. It was realized as a cavity with annihilation operator b :

$$\mathbf{C} = (-1, -\sqrt{0.2}b, 0) \boxplus (1, \sqrt{1.8}b, 0) \boxplus (1, \sqrt{0.2}b, 0).$$

□

V. CONCLUSIONS

In this paper we have given a description of quantum dissipative systems that combines perspectives from the quantum physics and control engineering communities. The quantum systems we considered are open quantum models, and with the aid of recently developed methods for describing quantum networks, we have shown how to describe external influences as arising from interactions with exosystems. The fundamental dissipation property was expressed in these terms. We presented an infinitesimal characterization of the dissipation property, which generalizes the well-known Positive Real and Bounded Real Lemmas. We also showed how to implement Willems' "control by interconnection" for open quantum systems using quantum network representations.

We believe that the results in this paper provide useful methods for the analysis and design of quantum dissipative systems, and indeed networks of such systems. The quantum network based results we have presented are quite general and powerful, and merit further development. The network paradigm is particularly important if quantum technology is to move from the device and small system level to a more complex system level such as is being contemplated, for example, in the quantum computing community.

APPENDIX

In this appendix we review some definitions and results concerning operator ordering.

Let A and B be self-adjoint operators on a Hilbert space \mathfrak{h} . Then by definition $A \geq 0$ means $\langle \psi, A\psi \rangle \geq 0$ for all vectors $\psi \in \mathfrak{h}$. Using this, we say $A \geq B$ to mean $A - B \geq 0$.

Now fix A and B self-adjoint, and C is arbitrary. Assume

$$w^*Aw \leq B + w^*C + C^*w \tag{74}$$

for all operators w acting on \mathfrak{h} . Then we claim that $A \leq 0$.

To verify this claim, suppose by contradiction there exists $\psi_0 \in \mathfrak{h}$ such that

$$\langle \psi_0, A\psi_0 \rangle > 0. \tag{75}$$

Now set $w = \alpha I$, where α is an arbitrary real number. Then (74) implies

$$\alpha^2 \langle \psi_0, A\psi_0 \rangle \leq \langle \psi_0, B\psi_0 \rangle + \alpha \langle \psi_0, (C + C^*)\psi_0 \rangle. \tag{76}$$

Since α is arbitrary, this contradicts (75), establishing the claim.

Now fix arbitrary operators C and D . We can use a similar argument to show that if

$$w^*C + C^*w \leq D \tag{77}$$

for all operators w acting on \mathfrak{h} , then $C = 0$.

REFERENCES

- [1] H. Carmichael. *An Open Systems Approach to Quantum Optics*. Springer, Berlin, 1993.
- [2] H.J. Carmichael. Quantum trajectory theory for cascaded open systems. *Phys. Rev. Lett.*, 70(15):2273–2276, 1993.
- [3] C. D’Helon and M.R. James. Stability, gain, and robustness in quantum feedback networks. *Phys. Rev. A.*, 73:053803, 2006.
- [4] A.C. Doherty and K. Jacobs. Feedback-control of quantum systems using continuous state-estimation. *Phys. Rev. A*, 60:2700, 1999. quant-ph/9812004.
- [5] P. Dupuis, M.R. James, and I.R. Petersen. Robust properties of risk-sensitive control. *Math. Control, Systems and Signals*, 13:318–332, 2000.
- [6] W. Fleming and M. James. The risk-sensitive index and the and norms for nonlinear systems. *J. Mathematics of Control, Signals, and Systems*, 8:199221, 1996.
- [7] A. Frigerio. Stationary states of quantum dynamical semigroups. *Commun. Math. Phys.*, 63:269–276, 1978.
- [8] C.W. Gardiner. Driving a quantum system with the output field from another driven quantum system. *Phys. Rev. Lett.*, 70(15):2269–2272, 1993.
- [9] C.W. Gardiner and M.J. Collett. Input and output in damped quantum systems: Quantum stochastic differential equations and the master equation. *Phys. Rev. A*, 31(6):3761–3774, 1985.
- [10] C.W. Gardiner and P. Zoller. *Quantum Noise*. Springer, Berlin, 2000.
- [11] J. Gough and M.R. James. The loading product and its application to quantum feedforward and feedback networks. 2007.
- [12] M. Green and D.J.N. Limebeer. *Linear Robust Control*. Prentice-Hall, Englewood Cliffs, NJ, 1995.
- [13] D. Hill and P. Moylan. The stability of nonlinear dissipative systems. *IEEE Transactions on Automatic Control*, AC-21:708–711, 1976.
- [14] D. Hill and P. Moylan. Dissipative dynamical systems: Basic input-output and state properties. *Journal of the Franklin Institute*, 309:327–357, 1980.
- [15] R.L. Hudson and K.R. Parthasarathy. Quantum Ito’s formula and stochastic evolutions. *Commun. Math. Phys.*, 93:301–323, 1984.
- [16] M.R. James, H. Nurdin, and I.R. Petersen. H^∞ control of linear quantum systems. quant-ph/0703150 2007.
- [17] S. Lloyd. Coherent quantum feedback. *Phys. Rev. A*, 62:022108, 2000.

- [18] P.J. Moylan. Implications of passivity in a class of nonlinear systems. *IEEE Trans. Automatic Control*, 19(4):373–381, 1974.
- [19] H. Nyquist. Thermal agitation of electric charge in conductors. *Phys. Rev.*, 32:110–113, 1928.
- [20] R. Ortega and M.W. Spong. Adaptive motion control of rigid robots: A tutorial. *Automatica*, 25(6):877–888, 1989.
- [21] R. Ortega, A. J. van der Schaft, I. Mareels, and B. Maschke. Putting energy back in control. *IEEE Control Systems Magazine*, 21:18–32, April 2001.
- [22] R. Ortega, A. J. van der Schaft, B. Maschke, and G. Escobar. Interconnection and damping assignment passivity-based control of port-controlled Hamiltonian systems. *Automatica*, 38:585–596, 2002.
- [23] K.R. Parthasarathy. *An Introduction to Quantum Stochastic Calculus*. Birkhauser, Berlin, 1992.
- [24] H.L. Trentelman and J.C. Willems. H_∞ control in a behavioral context: The full information case. *IEEE Trans. Automatic Control*, 44(3):521–536, 1999.
- [25] H.L. Trentelman and J.C. Willems. Synthesis of dissipative systems using quadratic differential forms: Part II. *IEEE Control Systems Magazine*, 47(1):70–86, 2002.
- [26] A.J. van der Schaft. *L₂-Gain and Passivity Techniques in Nonlinear Control*. Springer Verlag, New York, 1996.
- [27] J.C. Willems. Dissipative dynamical systems - Part I: General theory. *Archive of Rational Mechanics and Analysis*, 45:321–351, 1972.
- [28] J.C. Willems. On interconnections, control, and feedback. *IEEE Trans. Automatic Control*, 42(3):326–339, March 1997.
- [29] J.C. Willems. Open dynamical systems and their control. *Documenta Mathematica*, Extra Vol. ICM(III):697–706, 1998.
- [30] J.C. Willems. Control as interconnection. In *Feedback Control, Nonlinear Systems and Complexity*, Lecture Notes in Control and Information Science. Springer, 2003.
- [31] J.C. Willems and H.L. Trentelman. Synthesis of dissipative systems using quadratic differential forms: Part I. *IEEE Trans. Automatic Control*, 47(1):53–69, 2002.
- [32] H. M. Wiseman and G. J. Milburn. All-optical versus electro-optical quantum-limited feedback. *Phys. Rev. A*, 49(5):4110–4125, 1994.
- [33] B. Yurke and J.S. Denker. Quantum network theory. *Phys. Rev. A*, 29(3):1419–1437, 1984.
- [34] G. Zames. On the input-output stability of time-varying nonlinear feedback systems Part I: Conditions derived using concepts of loop gain, conicity, and positivity. *IEEE Trans. Automat. Control*, 11(2):228–238, 1966.
- [35] K. Zhou, J. Doyle, and K. Glover. *Robust and Optimal Control*. Prentice Hall, NJ, 1996.