

# P1 Error: A Combination of Absolute and Relative Errors

PEICHEN XIE, Microsoft Research

We propose  $\frac{|x-y|}{1+|y|}$ , termed the “P1 error” or “plus-1 error”, as a metric of errors. It equals half the harmonic mean of absolute error and relative error, effectively combining their advantages while mitigating their limitations. The P1 error approaches absolute error when  $|y|$  is small, and approaches relative error when  $|y|$  is large. An  $\epsilon$  P1 error indicates that  $x$  is close to  $y$  at a tolerance level of  $\epsilon$ , in compliance with the “isclose” definition used in popular numerical libraries.

## 1 MOTIVATION

We denote the approximate value as  $x$  and the real value or the reference value as  $y$ . Absolute error  $|x - y|$  and relative error  $\frac{|x-y|}{|y|}$  are two standard error metrics. However, each has limitations that hinder their sole use for error measurement.

Absolute error is unsuitable for large numbers, as it can overstate the importance of an error when the numbers are large, even if the relative error is small. For instance, an absolute error of 2 between  $x = 1002$  and  $y = 1000$  is the same as that between  $x = 3$  and  $y = 1$ , but the relative error in the first case is only 0.2%, which is much less significant compared to the latter case.

Conversely, relative error is not appropriate for small numbers, as it exaggerates the error when the reference value is small. For example, the relative error between  $x = 0.0002$  and  $y = 0.0001$  is identical to the relative error between  $x = 2000$  and  $y = 1000$ , but the absolute error in the first case is merely 0.0001, which is far less significant compared to the latter case.

These examples illustrate why it is necessary to consider both absolute and relative errors when measuring errors. The challenge then becomes: Can we adopt a single metric that encompasses both error types?

In this paper, we introduce a new error metric, termed the “P1 error” or “plus-1 error”. This metric combines the advantages of both absolute error and relative error while mitigating their limitations. With the P1 error, we aim to provide a unified metric that is sufficient for error measurement.

## 2 DEFINITION AND PROPERTIES

We observe that the small value of the denominator of relative error  $\frac{|x-y|}{|y|}$  amplifies the error value between small numbers. Therefore, we aim to increase the denominator for small numbers. We also aim to preserve the magnitude of the denominator for large numbers to maintain the advantage of relative error.

To this end, we add one to the denominator of the relative error, resulting in the ratio of the absolute error to the sum of one and the absolute value of the reference value:

$$p_1(x, y) = \frac{|x - y|}{1 + |y|}$$

We call this new metric “P1 error” or “plus-1 error”, denoted by  $p_1(x, y)$ . This design prevents the denominator from being too small, and thus avoids large error value for small numbers.

This design is not arbitrary. Choosing one makes the P1 error approach absolute error for small reference values. In this case, one dominates the denominator, resulting in that the P1 error approaches absolute error when  $|y|$  approaches zero:

$$\lim_{|y| \rightarrow 0} p_1(x, y) = |x - y| \quad (\text{Property 1})$$




Fig. 1. The ratio of P1 error to absolute error (blue) and the ratio of P1 error to relative error (red).

Meanwhile, the P1 error preserves the magnitude of the denominator for large reference values, making it approach relative error as  $|y|$  dominates the denominator:

$$\lim_{|y| \rightarrow +\infty} p_1(x, y) = \frac{|x - y|}{|y|} \quad (\text{Property 2})$$

The P1 error equals half the harmonic mean of absolute error and relative error:

$$p_1(x, y) = \frac{1}{2} \times \frac{2}{\frac{1}{|x - y|} + \frac{|y|}{|x - y|}} \quad (\text{Property 3})$$

Therefore, the P1 error can be viewed as a smooth and balanced combination of absolute error and relative error. Specifically, we observe the ratio of P1 error to absolute error

$$k_{\text{abs}} = \frac{p_1(x, y)}{|x - y|} = \frac{1}{1 + |y|}$$

and the ratio of P1 error to relative error

$$k_{\text{rel}} = \frac{p_1(x, y)}{\frac{|x - y|}{|y|}} = \frac{1}{1 + \frac{1}{|y|}}$$

We find that both  $k_{\text{abs}}$  and  $k_{\text{rel}}$  are monotonic and smooth functions of  $|y|$ . When  $|y|$  approaches 0,  $k_{\text{rel}}$  approaches 0 and  $k_{\text{abs}}$  approaches 1; when  $|y|$  approaches  $+\infty$ ,  $k_{\text{rel}}$  approaches 1 and  $k_{\text{abs}}$  approaches 0. In addition,  $k_{\text{rel}}$  and  $k_{\text{abs}}$  are symmetric with respect to the line  $k = 0.5$ , as shown in Figure 1.

	Description
Property 1	The error approaches absolute error when $ y  \rightarrow 0$ .
Property 2	The error approaches relative error when $ y  \rightarrow +\infty$ .
Property 3	The error is a smooth and balanced combination of absolute and relative errors.
Property 4	An $\epsilon$ error implies that $\text{isclose}(x, y, \epsilon, \epsilon) = \text{True}$ .
Property 5	The error is well-defined when $y = 0$ .

Table 1. Properties of P1 error.

Next, we notice that the P1 error is meaningful. Note that

$$p_1(x, y) = \epsilon \Leftrightarrow |x - y| = \epsilon + \epsilon|y|$$

Therefore, an  $\epsilon$  P1 error indicates that  $x$  is close to  $y$  with a distance of  $\epsilon + \epsilon|y|$ . The distance consists of two part: the “absolute distance part”  $\epsilon$  and the “relative distance part”  $\epsilon|y|$ . It is exactly in alignment with the definition of “isclose” function in popular numerical libraries such as NumPy [1] and PyTorch [2]:

$$\text{isclose}(x, y, a, r) = \begin{cases} \text{True}, & \text{if } |x - y| \leq a + r|y| \\ \text{False}, & \text{otherwise} \end{cases}$$

The  $a$  parameter means absolute tolerance and the  $r$  parameter means relative tolerance. Hence, a P1 error of  $\epsilon$  implies that  $x$  is close to  $y$  at a absolute tolerance level of  $\epsilon$  and a relative tolerance level of  $\epsilon$ :

$$p_1(x, y) = \epsilon \Rightarrow \text{isclose}(x, y, \epsilon, \epsilon) = \text{True} \quad (\text{Property 4})$$

Lastly, unlike the relative error that is undefined when  $y = 0$ , the P1 error is well-defined for all  $x \in \mathbb{R}$  and  $y \in \mathbb{R}$ . Specifically,

$$p_1(x, 0) = |x| \quad (\text{Property 5})$$

Table 1 summarizes the properties.

### 3 EXAMPLES

With the five properties, P1 error can be a good substitute of absolute error and relative error. In this section, we demonstrate that absolute error works badly for large numbers, relative error works badly for small numbers, and P1 error works well consistently.

Table 2 shows examples of  $(x, y)$  and their errors measured with absolute error, relative error, and P1 error.

First, we fix the absolute error to 2 and set  $x = y + 2$  for  $y \in \{0.001, 1, 1000\}$ . For  $x = 2.001$  and  $y = 0.001$ , the relative error is 2000, which is enormous, while the P1 error is 1.998, offering a more reasonable measurement similar to the absolute error. For  $x = 3$  and  $y = 1$ , both the absolute error and the relative error are 2, and the P1 error is half of it. For  $x = 1002$  and  $y = 1000$ , the P1 error is 0.001998, which correctly reflects the smallness of the error as the relative error does.

Second, we fix the relative error to 0.02 and set  $x = 1.02y$  for  $y \in \{0.001, 1, 1000\}$ . For  $x = 0.00102$  and  $y = 0.001$ , both the P1 error and the absolute error reflect the tininess of the error. For  $x = 1.02$  and  $y = 1$ , both the absolute error and the relative error are 0.02, and the P1 error is half of it. For  $x = 1020$  and  $y = 1000$ , the absolute error is 20, which overestimates the error, while the P1 error, at 0.01998, more accurately reflects the error’s smallness, similar to the relative error.

	$x$	$y$	<b>Absolute error</b> $ x - y $	<b>Relative error</b> $\frac{ x - y }{ y }$	<b>P1 error</b> $\frac{ x - y }{1 +  y }$
Values with the same absolute error	2.001	0.001	2	2000 (200000%)	1.998
	3	1		2 (200%)	1
	1002	1000		0.002 (0.2%)	0.001998
Values with the same relative error	0.00102	0.001	0.00002	0.02 (2%)	0.00001998
	1.02	1	0.02		0.01
	1020	1000	20		0.01998
Values with the same P1 error	0.2012	0.001	0.2002	200.2 (20020%)	0.2
	1.4	1	0.4	0.4 (40%)	
	1200.2	1000	200.2	0.2002 (20.02%)	
$y = 0$	0.001	0	0.001	Undefined	0.001

Table 2. Examples measuring with different error metrics.

Third, we fix the P1 error to 0.2 and set  $x = 0.2 + 1.2y$  for  $y \in \{0.001, 1, 1000\}$ . For  $x = 0.2012$  and  $y = 0.001$ , the P1 error closely matches the absolute error, which is 0.2002. In contrast, the relative error is 200.2, significantly overestimating the error. For  $x = 1.4$  and  $y = 1$ , both the absolute error and the relative error are 0.4, and the P1 error is half of it. For  $x = 1200.2$  and  $y = 1000$ , the P1 error is close to the relative error of 0.2002, while the absolute error is 200.2, which is an overestimation.

When  $y = 0$ , the relative error is undefined, whereas the P1 error is well-defined and equal to the absolute error, which is  $|x|$ .

Among these examples, the largest P1 error occurs at  $x = 2.001$  and  $y = 0.001$ , corresponding to the largest relative error and a non-negligible absolute error. The smallest P1 error occurs at  $x = 0.00102$  and  $y = 0.001$ , corresponding to the smallest absolute error and a comparatively small relative error.

In these examples, the P1 error effectively avoids the exaggerated relative error for small reference values and the exaggerated absolute error for large reference values, capturing the significance of the error indicated by the other metric. Indeed, the P1 error is no greater than the minimum of absolute error and relative error, because  $k_{\text{abs}} \leq 1$  and  $k_{\text{rel}} < 1$ .

## 4 DISCUSSION

This section discusses other combinations of absolute error and relative error and shows that the P1 error is the better than them.

### 4.1 Plus- $t$ errors

We can view the P1 error as a smoothed relative error with the smooth factor of one added to the denominator of the relative error. Naturally, we can choose other smooth factors other than one, resulting “plus- $t$ ” errors

$$p_t(x, y) = \frac{|x - y|}{t + |y|}, t \neq 1$$

However, for plus- $t$  errors, Property 1 no longer holds, as

$$\lim_{|y| \rightarrow 0} p_t(x, y) = \frac{|x - y|}{t} \neq |x - y|$$




Fig. 2. The ratio of max-1 error to absolute error (blue) and the ratio of max-1 error to relative error (red).

Property 3 no longer holds, either, indicating that plus- $t$  errors are imbalanced combination of absolute and relative errors. Property 4 has to be modified to

$$p_t(x, y) = \epsilon \Rightarrow \text{isclose}(x, y, \epsilon t, \epsilon) = \text{True}$$

#### 4.2 Max-1 error

If we change the addition operation in P1 error to maximum, we can have the “max-1” error

$$m_1(x, y) = \frac{|x - y|}{\max(1, |y|)}$$

For max-1 error, Property 1 and Property 2 still hold, but Property 3 does not. Considering that

$$k_{\text{abs}} = \frac{m_1(x, y)}{|x - y|} = \frac{1}{\max(1, |y|)}$$

and

$$k_{\text{rel}} = \frac{m_1(x, y)}{\frac{|x - y|}{|y|}} = \frac{|y|}{\max(1, |y|)}$$

are non-smooth and asymmetric functions, the max-1 error is a unsmooth and imbalanced combination of absolute and relative errors, as shown in Figure 2.

Property 4 does not hold for max-1 error; instead, it has to be modified to

$$m_1(x, y) = \epsilon \Rightarrow \text{isclose}_2(x, y, \epsilon, \epsilon) = \text{True}$$

	Property 1	Property 2	Property 3	Property 4	Property 5
P1 error	yes	yes	yes	yes	yes
Plus- $t$ errors	no	yes	no	variant	yes
Max-1 error	yes	yes	no	variant	yes

Table 3. Comparison between error metrics.

where

$$\text{isclose}_2(x, y, a, r) = \begin{cases} \text{True,} & \text{if } |x - y| \leq \max(a, r|y|) \\ \text{False,} & \text{otherwise} \end{cases}$$

is a variant of isclose function.

In summary, Table 3 compares plus- $t$  errors and max-1 error with P1 error. The P1 error retains all five desirable properties, unlike plus- $t$  errors and max-1 error, which fail to satisfy certain properties.

## 5 CONCLUSION

This paper has presented the P1 error, an error metric with five useful properties. It combines the advantages of absolute and relative errors, and thus can be used as a single metric to measure errors.

## REFERENCES

- [1] Charles R. Harris, K. Jarrod Millman, Stéfan van der Walt, Ralf Gommers, Pauli Virtanen, David Cournapeau, Eric Wieser, Julian Taylor, Sebastian Berg, Nathaniel J. Smith, Robert Kern, Matti Picus, Stephan Hoyer, Marten H. van Kerkwijk, Matthew Brett, Allan Haldane, Jaime Fernández del Río, Mark Wiebe, Pearu Peterson, Pierre Gérard-Marchant, Kevin Sheppard, Tyler Reddy, Warren Weckesser, Hameer Abbasi, Christoph Gohlke, and Travis E. Oliphant. 2020. Array programming with NumPy. *Nature* 585 (2020), 357–362. <https://doi.org/10.1038/S41586-020-2649-2>
- [2] Adam Paszke, Sam Gross, Francisco Massa, Adam Lerer, James Bradbury, Gregory Chanan, Trevor Killeen, Zeming Lin, Natalia Gimelshein, Luca Antiga, Alban Desmaison, Andreas Köpf, Edward Z. Yang, Zachary DeVito, Martin Raison, Alykhan Tejani, Sasank Chilamkurthy, Benoit Steiner, Lu Fang, Junjie Bai, and Soumith Chintala. 2019. PyTorch: An Imperative Style, High-Performance Deep Learning Library. In *Conference on Neural Information Processing Systems (NeurIPS)*. 8024–8035. <https://proceedings.neurips.cc/paper/2019/hash/bdbca288fee7f92f2bfa9f7012727740-Abstract.html>