

A Quantum ISA for High-Level Programming, Enabling Sequential Execution and Conditional Branching

Francesco Junior De Gregorio

September 2024

Abstract

This paper introduces a novel quantum instruction set architecture that abstracts quantum circuits to support high-level programming paradigms, including sequential execution and branching. By separating concerns between hardware and software, the proposed architecture simplifies quantum algorithm development, allowing programmers to work with classical structures while still being able to exploit quantum-specific behavior. This abstraction enables developers to focus on algorithm design without being burdened by low-level circuit construction, thus facilitating both hardware optimization and software innovation. The proposed architecture represents a step forward in bridging the gap between classical and quantum programming.

Contents

1	Introduction	1	4	Memory access	4
2	Definition of Execution and Conventions	3	4.1	Traversing	5
2.1	Execution overview	3	4.2	Qubit Activation	5
2.2	Reversing Convention	3	4.3	Readout	5
2.3	Parallel Computation	4	5	Control Unit	5
2.4	Instruction build	4	5.1	Demultiplexer	6
3	Types of buses	4	5.2	Register Access	6
3.1	Cnot copy	4	5.3	Direction Zone	6
3.2	Swap reference	4	6	Gate structure	6
			7	Assembly language definition	8
			7.1	General syntax	8
			7.2	If statement	8
			7.3	Do while loop	8
			7.4	Function call	9
			8	Definition of garbage	10
			8.1	Garbage Cleaning Algorithm	10
			9	ONDA programming language	11
			9.1	Classical syntax	11
			9.2	Quantum syntax	11
			9.3	Code example	12
			10	Future outlooks	12
			11	Conclusion	12
			1	Introduction	
				Quantum computers in the current NISQ era are noisy, error-prone, and incapable of executing many	

operations before decoherence occurs. However, the field is experiencing tremendous growth, with promising road maps guiding future advancements. In recent years, remarkable achievements have been made [1, 4–6, 10], and small-scale quantum computers are increasingly becoming available for public research. This growing accessibility highlights the need for expertise in the field. In response, companies have begun lowering the knowledge barrier for programming quantum computers and have introduced educational programs. However, these efforts are still aimed at specialized individuals with a scientific background.

Unlike classical programming, which has become widely accessible, quantum programming remains limited due to its low-level interface—requiring users to build circuits directly. One key factor behind the exponential growth of classical computing is the ability to create multiple layers of abstraction, allowing programmers to work at higher levels without needing to understand every underlying detail. This work proposes an architecture that introduces similar layers of abstraction for quantum computing, enabling sequential execution and branching through a high-level quantum programming language.

Previous quantum programming languages have primarily functioned as interfaces for constructing quantum circuits. In contrast, the ONDA programming language enables the development of programs in binary format. These programs are executed by a quantum architecture specifically designed to sequentially execute instructions using quantum gates, which perform the entire computational process. In this work is discussed a simple hardware scheme and the software interface to program it. Section 2 gives a general overview of how the architecture works. Section 3 discusses different methods for transmitting quantum information, Section 4 explains memory access, Section 5 covers how information is routed to an ALU and Section 6 defines a convention to build gates in it. Section 7 and Section 9 define and explore respectively the ISA and the ONDA programming language, while Section 8 addresses challenges encountered during the research.




Figure 1: The diagram presents an abstract representation of the architecture by attempting to physically separate its components. However, complete separation is not feasible; for instance, the direction zone, which conceptually is in the control unit, is illustrated within the ALU due to its close interaction with it.

2 Definition of Execution and Conventions

2.1 Execution overview

The quantum architecture incorporates a primary operation, denoted as S , which modifies qubits across various components of it. This operation is executed i times, after which a measurement operation M is performed, where i is an high enough number to be sure that all the parallels computations are completed. The architecture follows a modified Harvard architecture, comprising four main components as in Figure 1: program memory, registers, the ALU, and two memory units.

In the program memory, a program is written as a sequence of bytes, which is loaded once at the commencement of computation. A reserved buffer house the program counter (PC), which points to the current instruction. The operation S consists of a sequence of actions across different areas. The initial step of S involves reading the instruction indicated by the PC in a QRAM-like fashion [7], temporarily storing it in an instruction buffer. Subsequently, the control unit decodes the instruction and outputs k qubits, where k is the number of operation codes available. Those qubits are referred to as activation qubits, which signify the activation of specific instructions. Each of these qubits serves as the control qubits for the controlled operations employed to execute the associated instruction.

Following the decoding process, the control unit accesses the values from the registers specified by the instruction. These values, along with the activation qubits, are transmitted either to the ALU for arithmetic operation, or to memory for execution of save/load/read instructions¹. Each instruction is executed in a designated region of the QPU and is structured to have n input registers, m output registers, and k ancilla registers. The control unit must supply the gate with the qubits on which the output will be computed, as well as at least one copy (defined in

Section 3.1) of the input qubits.

Upon completion of the operation, all routing operations are reversed, and the modified values return to their respective registers. Additionally, the activation qubits are reversed to zero. Utilizing the address contained in the PC, the qubits in the instruction buffer are returned to the program memory. It is important to note that the PC cannot be altered during computation; modifying it would prevent the ability to save the instruction back into memory. Therefore, an update register (UR) is necessary. The UR gets added to the PC at the conclusion of each cycle and is initially set to 1. By dynamically adjusting the value of the UR during computation, it becomes possible to construct abstract control structures such as IF statements, DO WHILE loops, and jumps. To maintain consistency in gate execution, it is essential that all ancilla qubits are in the same state at both the beginning and the end of S ; thus, the REVERSING convention is established.

2.2 Reversing Convention

Each gate is designed to have a base state, usually with all ancilla qubits set to 0, upon the computation relies. Corruption of this base state could led to wrong output. To address this issue, the reversing convention is followed, it states:

Convention *each operation necessitates a forward pass and a reverse pass. The forward pass computes the output utilizing and modifying the ancilla and/or input qubits. The reverse pass will restore all the ancilla and/or input qubits to the their base state without altering the output qubits.*

By following this convention, one can reliably ascertain the state of the gate when an input is received. In the subsequent sections, the discussion of gates will also include an explanation of how to implement the reverse pass.

¹notably, the only permissible memory operation is the swap operation

2.3 Parallel Computation

This paper will focus exclusively on scenarios in which the machine is in a basis state. Nevertheless, the computational scheme remains valid for states in superposition. Specifically, different computations can be performed in parallel without unintended interference between states. Let $|a\rangle, |b\rangle \in \Sigma$ where Σ represent the set of basis states. Up to normalization:

$$\begin{aligned} S^i |a\rangle &= |\psi_1\rangle \\ S^i |b\rangle &= |\psi_2\rangle \\ |\phi\rangle &= |a\rangle + |b\rangle \\ S^i |\phi\rangle &= |\psi_1\rangle + |\psi_2\rangle \end{aligned}$$

2.4 Instruction build

The definition of how an instruction is structured falls outside the scope of this research. Future hardware may have specific requirements that manufacturers will need to address in order to optimize the execution of the QPU. This architecture is intended to be applicable to both 32-qubit and 64-qubit, or even larger, processors. However, for the sake of simplicity, I describe a 32-qubit QPU with 32 registers.

The 32-qubit QPU presented in this paper features a simple instruction structure. The first 6 qubits are reserved for the opcode, which determines the specific gate to which the data will be directed. The subsequent 26 qubits are utilized for indexing the $n + m$ registers on which the operation will be performed, where n represent the number of input registers and m represent the number of output registers. Each index requires 5 qubits, as there are 32 registers available. The remaining $32 - 5n - 5m$ qubits may serve as offsets for the indices or as options for the gates; In the absence of specific assignments, these qubits will default to a value of 0. It is important to note that while n and m can vary to accommodate multiple uses, the opcode remains the only fixed component.

3 Types of buses

The QPU comprises many error-corrected qubits that remain stationary while the information is transmitted. Various methods can be employed to facilitate the movement of information between different areas.

3.1 Cnot copy

An efficient method for moving information is to utilize a series of CNOT gates applied to ancilla qubits initialized to 0. However, during computation, the bus cannot be reused, as all the qubits are occupied by the values of the original data. Once the information reaches its destination, it can only be read; any modification would preclude the ability to reverse the operation. To perform the reverse pass, one simply needs to apply the same gates in reverse order. This method of information transmission will be referred to as "copy," as one cannot modify the original value but rather possesses a view of it.

3.2 Swap reference

Utilizing a similar structure to the previous method, a series of swap gates can also be employed. Although this approach is slower—approximately three times slower than the CNOT copy—it provides a greater degree of freedom. The bus can be reused while the data is being processed by the computation. Furthermore, one can modify the data or swap it with other information to execute move operations. The reverse pass involves applying the same set of gates in the opposite order. This method of information transmission will be referred to as "reference," as it allows for manipulation of the actual values stored in the source qubits.

4 Memory access

Various proposed QRAM architectures fulfill the necessary conditions for the effective operation of this area QCPU [7, 12]. In this section, I will discuss a simplified, albeit costly, implementation to provide the reader with a comprehensive overview of the architecture.

4.1 Traversing

Once the input address has been copied into the input register, it is transmitted to the corresponding memory location. This process is accomplished by traversing a balanced binary tree according to the path defined by the address: at the n th layer, the input address will take the left fork if the n th qubit is 0, or the right fork if it is 1. In Figure 2 a layer of the tree is implemented.

4.2 Qubit Activation

Once the address reaches the memory location, it must activate the corresponding activation qubit. As Figure 3 shows, given that the base ancilla register (the one that will substitute for the address if it does not arrive) is initialized to the all-zero string, a controlled NOT operation on the activation qubit, with control provided by a qubit set to 1 in the address, will suffice to correctly activate the activation qubit.

4.3 Readout

At this stage, there is only an activation qubit turned on within a memory filled with activation qubits that are turned off. To efficiently read out the output in $O(n)$ time additional $\sum_{i=1}^{n-1} 2^i$ data registers are required, where n is the number of qubits the address has. The data will traverse a readout balanced binary tree, where each node contains an activation qubit and a data register. For each layer, the data is swapped with the higher-level register only if the activation qubit is turned on. Simultaneously, the activation qubit is transmitted by applying a logical OR operation between the activation qubits of neighboring nodes. Let U represent the entire access operation; then, $U^\dagger$ denotes the reverse pass of the operation.

5 Control Unit

The Control Unit (CU) comprises three key components: the demultiplexer, the register access area, and the direction zone. The demultiplexer activates the activation qubit corresponding to the opcode. The register access area loads values onto the bus from




Figure 2: circuit that implement the fork at layer 1 of a 3 qbit address. The qubit at the corresponding index gets copied to an ancilla that become the control to a swap operation that move the address from a register to another.




Figure 3: circuit to activate the activation qubit of address 110, one can just use the one in index 2 without referring to the other qubits

the registers specified by the instruction. The direction zone directs the values from these registers to the zone of the ALU associated with the activated activation qubit. Additionally, the CU is responsible for updating the PC at the end of each cycle by incrementing it with the value stored in the update register.

5.1 Demultiplexer

After the instruction has been read and copied into the instruction buffer, it will be passed through a demultiplexer that flips the activation qubit corresponding to the opcode. To construct a demultiplexer as in Figure 4, fan-out gates, NOT gates, and multi-input AND gates are required. The classical fan-out gate can be implemented using a quantum controlled-NOT (CNOT) gate, the classical NOT gate can be realized with a quantum X gate, and the classical multi-input AND gate can be constructed using a quantum multi-controlled NOT gate.

Each of these gates is its own inverse; therefore, to perform a reverse pass, one can simply apply the same gates in reverse order.

5.2 Register Access

The remaining 26 qubits of the instruction, along with the 64 activation qubits, are transmitted to the register memory. Upon arrival, the values stored in the registers indicated by the indexes are loaded into a bus. The activation qubits serve as control for the swaps between the indices specified in the instruction and the input (or address) buffer in the access operations of the registers². The output is directed to the output zone, comprising $n + m + 1$ 64-qubit values (quadwords): n read-only (passed by copy) input quadwords, m read-write (passed by reference) output quadwords and 1 quad-word consisting of activation qubits. Here n and m depend on the executed instruction. The bus will have as many channels as required by the instruction with the highest number of inputs. The reverse pass will follow the same procedure as described in Section 4 and Section 3

²note that different instructions, and consequently different activation qubits, have distinct methods for defining the

5.3 Direction Zone

The direction zone contains a main bus through which the $n + m + 1$ qwords are transmitted. As the data progresses, whenever the bus encounters a gate, it performs a controlled swap between the real data and the gate's input/output buffer, with the corresponding activation qubit acting as the control. Each gate, as discussed in Section 6, has an input/output buffer where it expects its data to be stored. This buffer typically contains ancilla qubits (such as registers initialized to zero) that are used for computation unless swapped with real data. If a swap is triggered, the ancilla qubits replace the real data on the main bus. However, since only one activation qubit is turned on per instruction, these ancilla qubits do not serve as input to any other gate and will return to their original position during the reverse pass. The reverse pass is achieved by executing all gates in reverse order.

6 Gate structure

Gates form the fundamental building blocks of the QPU and are the only components that perform both forward and reverse passes sequentially. The construction of optimized base gates is crucial for achieving fast execution, as S is performed many times per second and they represent the longest operation within it. Many circuits that can be thought of as basic instructions for an ISA have been researched [3, 11, 13]. However, adherence to established conventions is essential for efficient coordination between components. Each gate in this structure contains an input buffer, which is divided into two parts: one for read-only input values and another for read-write values, where the output of the computation is stored. Additionally, the gate employs ancilla qubits to facilitate computation. Although gates can be designed so that the ancillas do not always return to their base state for certain applications, this paper focuses exclusively on gates that reset their ancilla qubits to their original state at each cycle.

registers to access, so more than one access operation may be defined.




Figure 4: This graph represent how a demultiplexer is built, biforking arrows are implemented as quantum fan out (cnot) gates and the crossed circle before the and gates indicate negation




Figure 5: Direction zone for a subset of gates, where the empty circle with an arrow indicates a controlled swap gate between the real data and the input/output buffer's ancillas

7 Assembly language definition

7.1 General syntax

Programs stored in program memory must be encoded in binary format. To facilitate this, an assembly language serves as interface, allowing the programmer to write code in a more human-readable format. This assembly code is then classically translated into a sequence of bytes. An assembly program consists of a series of lines, each representing a distinct instruction. The format of an instruction is

$\langle \text{instruction} \rangle \langle \text{inputs} \rangle$

$\langle \text{instruction} \rangle$ serves as the identifier for the operation. $\langle \text{inputs} \rangle$ consist of a series of tokens that can represent either registers (denoted by their aliases in Table 1) or immediate values (represented by numerical values). An assembly code example is given below.

```
addi $t1, 6
add  $t2, $t1
```

In this program the first instruction add 6 to $\$t1$ ³. Then the second instruction add $\$t1$ to $\$t2$. The assembly language in [8] includes more than 40 instructions, all of which can be implemented using a quantum circuit who adheres to the previously defined conventions.

7.2 If statement

The two branches of the if statement are represented by conditional additions to the update register. Each

³In this paper, any reference to a register alias actually refers to the value stored in the register.

jump consists of two additions: one to activate and perform the jump, and another to deactivate it. It is crucial to avoid modifying the condition within the if block. If the value of the condition changes inside the if block, the program may enter an infinite loop. To address this issue, one can leave the condition variable unchanged and use a copy of it. Once outside the block, the original condition variable can either be discarded or devaluated to avoid creating garbage (defined in Section 8).

```
# eval condition
caddi not cond $ur +x
# ...true body with length x...
caddi not cond $ur -x
caddi cond $ur +y
# ...false body with length y..
caddi cond $ur -y
# deval condition or
# trash(ta) condition
```

The operation `caddi` is the conditional add immediate instruction, it adds the third register to the second if the value of the first qubit of the first register is 1.

7.3 Do while loop

The algorithm presented in [8] is outlined in this section. For the sake of clarity, a simplified version of the algorithm is provided in pseudocode rather than in assembly language.

```
x = BODYLENGTH + 1
tur1 = 1
tur2 = -x+1
counter = 0
activation = False
# tcsu
# it is one single asm instruction
{
  if counter % 2 == activation:
    swap ur tur1
    flip activation
  else
    swap ur tur2
    flip activation
}
```

Table 1: ?isaname? Registers aliases

REGISTERS INDEXES	REGISTER ALIASES	REGISTER NAMES
0	\$zero	0 registers
1	\$ur	update register
2	\$tur	temporary update register
3-4	\$v0-\$v1	return values
5-8	\$a0-\$a3	argument regs
9-18	\$s0 - \$s9	saved regs
19-27	\$t0-\$t8	temporary regs
28	\$grp	garbage pointer
29	\$sp	stack pointer
30	\$fp	frame pointer
31	\$ra	return address

```

# tcai
if counter % 2 == 0:
    addi tur2 x
else
    addi tur1 x

# set tur1 = 0 only
# at the first iteration
if counter == 0
    addi tur1 -1

.....
body
.....

increment counter
if arbitrary condition:
    addi ur -x

```

The algorithm uses two temporary update registers, to jump back to the initial instruction if the condition is satisfied. The two registers are alternately set to $-x+1$ and 1, the negative one will be used to perform the jump, and the one set to 1 will be used to go to the next instruction. At the start of each cycle the two registers are restored to those values. Note that the “tcsu” (two-case swap update register) could be implemented as an if statement. However, the algorithm leverages the fact that if the \$ur is set to zero, the instruction will be executed again. An implemen-

tation using traditional IF constructs cannot achieve this behavior.

7.4 Function call

The following pseudocode implements only the jump section of a function call, omitting the declaration of other constructs, such as an activation frame, as these are outside the scope of this paper.

```

qfun: # line_num = f_pc
      swap ur tur

qret:
      tur *= -1
      tur -= fun.len
      tur += 1
      swap ur tur

qcall:
      # save the old tur
      # and set tur to 0
      swap tur, stack[sp]
      addi sp 1
      tur += f_pc - pc
      swap ur tur
      # reversing to
      tur -= pc - f_pc - fun.len
      # set tur to the
      # original value

```

```

addi sp -1
swap tur, stack[sp]

```

8 Definition of garbage

Quantum ISAs introduce challenges that classical ISAs did not have to address. Operations like the "save word," "load word," and "jump" instructions are not unitary operations and cannot be directly implemented in a quantum architecture. However, in many quantum computing procedures, qubits initialized to 0 must be used. Additionally, some values are only needed for small portions of a computation and can be discarded once they are no longer useful. Unfortunately, this operation is not unitary and cannot be performed on a quantum computer without causing interference or collapsing the parallel computations. To address this issue, a new 0-initialized memory, referred to as the "garbage," is defined. This memory stores the garbage stack, the top of which is pointed to by the garbage pointer (\$grp). To set any value to zero, the value is swapped with the top of the garbage stack, and the garbage pointer is updated accordingly. This operation is executed by the single "ta" instruction, although in practice, multiple instructions may be required to perform this task.

8.1 Garbage Cleaning Algorithm

A Garbage Cleaning algorithm is a procedure that reduces the size of the garbage stack by mapping most of its values to 0 in a unitary manner. It is implemented as a function that is called periodically, either dynamically (within the program written by the user) or automatically (by the compiler). The garbage cleaning algorithm proposed in [8] consists of two steps: the sorting step and the cleaning step.

In the sorting step, all qubits in the garbage stack are sorted in descending order. The algorithm in [8] results in the creation of two arrays, whose combined size equals $64 \times n$, where n is the size of the original stack. These arrays are naturally sorted as a byproduct of the process, without requiring additional sorting. Alternatively, any sorting algorithm, such as the

one in [2], could be implemented at this stage, provided that the number of garbage values generated in doing so remains less than n .

The cleaning step set to zero the two arrays with creation of little garbage. To clean the original garbage stack, that is now sorted, it flips the first m qubits, where m is dynamically calculated within the program and represents the total number of 1s in the stack. To clean the two larger arrays, the algorithm uses a counter to identify and set each value equal to it to 0, and then increments the counter. Python pseudo code for this step is provided below.

```

# arr is the array to clean
# bin_arr is a temporary array
while arr_index < len(arr):
    while bin_index != len(bin_array) \
        and arr_index < len(arr):
        increment loop_counter
        if arr[arr_index] == counter:
            Toggle activation

    if activation is True:
        Swap(bin_arr[bin_index],
            and arr[arr_index])

    if bin_arr[bin_index]==counter:
        Toggle activation

    Increment arr_index
    Increment bin_index

Decrease loop_counter by bin_index
Decrease bin_index by len(bin_arr)

IF counter <= massimo:
    Count occurrences of 0 in bin_arr
    and store in zeros_count
    Decrease arr_index by zeros_count
    Subtract the same number of 0
    occurrences from zeros_count

Reset elements in bin_array
equal to counter to 0
# this reset is done by doing
# a series of nulling

```

```
# cnot starting from the 0 index.
# the 0 index will be nulled
# by the counter
```

Increment counter

The algorithm keeps track of a counter and two pointers, the array pointer(that points to the current examined value) and the bin array pointer(that points to the top of the bin array). At each value of the counter the following procedure is followed. The array pointer is incremented, then if the value pointed by it is equal to the counter, it is swapped with the top of the bin array (that is equal to 0) while incrementing the bin array pointer. This procedure will fill the bin array with all the instances of values of the array equal to counter . Then a series of cnots is performed with the value at index $n - 1$ as control, and the value at index n as target $\forall n \in \{N, N - 1, \dots, 1\}$ where N is the size of the bin array. The value at index 0 will be the target of a cnot with the counter as control. To make the algorithm more efficient the bin array has size equal to the modal frequency of the array. Note that the DO WHILE loop creates one garbage value: the number of times it has been executed. To avoid creating more garbage by throwing it into the garbage array, one can set it back to zero at each iteration. ONDA has a specific syntax to access and reverse the hidden underlying loop counter; if not specified, it would throw it away automatically. This example shows only how to calculate and reverse a variable loop counter, which can be used to reverse the hidden loop counter.

The same mirrored algorithm is applied to the second array, which is sorted in ascending order.

9 ONDA programming language

The ONDA programming language is designed to provide an environment in which programmers can disregard garbage handling and focus solely on writing code. ONDA resembles a C-like programming language and shares many of its features; therefore, the classical aspects will be briefly discussed while

placing greater emphasis on the unique quantum features.

9.1 Classical syntax

```
// ONDA CODE EXAMPLE
int a; // same as a = 0
int b = 3;
float c; // same as c = 0.0
float d = 4.5;
int arr1[32];
float arr2[32];
a += 2;
a += b;
a = (b + 4) * 2;
arr[a] = 2;
if(condition1){
// do something
}else{
// do something else
}
do{
// ... computation ...
}while(condition2);

_clean_garbage();
```

Operators +=, -= are supported without garbage creation, while *=, /=, %= create garbage. Re-assignment ($a = b$) create garbage. Inline expression like $2 + a * (b/4 - 1)$ don't create garbage. Function calls and definitions are equal to C. For further details see [8].

9.2 Quantum syntax

In ONDA, three quantum operations are defined: X, Z, and H.

The X operation is represented by the $\sim$ operator and functions identically to its classical counterpart in the C programming language.

```
// a = int max
unsigned int a = ~0;

// a = 0
a ~ = 0;
```

The Z operation is denoted by the “#” operator. In an expression such as $a\#b$, a Z gate is applied to the first b qubits of the value a , starting from the least significant bit (LSB). Similarly, the H operation is denoted by the “@” operator. In an expression such as $a@b$, a Hadamard gate is applied to the first b qubits of the value a . By combining these operators, one can construct a wide range of programs.

```
int a = 0 @ 6;
a @= 2;
a += 1;
a #= 1;
```

At the start, the state of a is a superposition of the values from 0 to 64. Then it becomes a superposition of the values from 0 to 64 that are multiple of 4. Since the LSB is 0, the instruction $a+ = 1$ will flip the last qubit. The last instruction will perform a Z gate on the LSB kicking a phase into the system

9.3 Code example

This example demonstrates the implementation of the Grover’s search algorithm on an unstructured database [9].

```
int arr_length = 256;
int index = 0;
int searched_number = 36;
int iteration = 0;
int minus = 1;

minus @= 1; // initialize minus state
index @= 8; /* super impose all the
             indexes from 0 to 255*/
do{
    if(arr[index] == searched_number){
        /* in place xor with one,
        kick back the phase */
        minus ^= 1;
    }
    index @= 8;
    if(index == 0){
        /* in place xor with one,
        kick back the phase */
        minus ^= 1;
    }
}
```

```
}
index @= 8;
iteration += 1;
}while(iteration < sqrt(arr_length));

measure(index)
/* the most probable measure is
the index of 36*/
```

10 Future outlooks

Modern ISAs are significantly more complex and optimized compared to the proposed quantum ISA. However, in the future, many classical features may be translatable into their quantum counterparts. Additionally, entirely new approaches could emerge by leveraging the unique behaviors of quantum mechanics. For instance, it might be possible to develop new bus architectures based on quantum teleportation protocols as [14].

Further advancements are likely to occur in the hardware-software co-design of QPUs. One potential direction is to leave some opcodes unused, allowing programmers to define and dynamically invoke custom quantum gates within the architecture.

This proposal is also open to numerous, hardware and software, optimizations and standardization efforts across various areas. For example, determining the optimal number i of iterations for the step operation, S , to be performed before measurement M remains an unresolved issue. Future research can also explore high-level quantum programming languages, such as ONDA, to discover new application domains and enhance the software ecosystem surrounding quantum computing.

11 Conclusion

This paper discusses a quantum microarchitecture that implements a Turing-complete quantum computer. A sequence of operations that execute an instruction stored in program memory has been defined. The implementation of several components is addressed, including: a program memory where

instructions are read; a control unit, along with its sub-components, that directs data to the appropriate region of the ALU based on the given instruction; and an ALU that performs the current instruction, along with a convention for constructing operations within it.

Furthermore, a quantum ISA is defined, outlining the supported instructions. Algorithms for performing control constructs such as IF statements, DO WHILE loops, and function calls are described using the assembly language specified by the ISA. Additionally, issues related to data creation and destruction, along with potential solutions, are discussed. The quantum programming language, ONDA, is introduced, and examples of its syntax are provided. The work highlights issues that remain open for future research, particularly in areas such as optimization and standardization.

An error-corrected quantum computer capable of executing this architecture is unlikely to emerge before the next decade. This paper establishes the foundation for building a broader framework that reduces the barriers to entry in quantum computing while also accelerating progress in the field. The ultimate goal is to be prepared for when such technology becomes available.

References

- [1] Jacob Biamonte, Peter Wittek, Nicola Pancotti, Patrick Rebentrost, Nathan Wiebe, and Seth Lloyd. Quantum machine learning. *Nature*, 549(7671):195–202, Sep 2017.
- [2] Sheng-Tzong Cheng and Chun-Yen Wang. Quantum switching and quantum merge sorting. *IEEE Transactions on Circuits and Systems I: Regular Papers*, 53(2):316–325, 2006.
- [3] Thomas G. Draper. Addition on a quantum computer, 2000.
- [4] Frank Arute et al. Quantum supremacy using a programmable superconducting processor. *Nature*, 574(7779):505–510, 2019.
- [5] E. Farhi, J. Goldstone, S. Gutmann, and H. Neven. Quantum algorithms for fixed qubit architectures, 2017.
- [6] Edward Farhi, Jeffrey Goldstone, and Sam Gutmann. A quantum approximate optimization algorithm, 2014.
- [7] Vittorio Giovannetti, Seth Lloyd, and Lorenzo Maccone. Quantum random access memory. *Phys. Rev. Lett.*, 100:160501, Apr 2008.
- [8] Francesco Junior De Gregorio. Onda programming language. <https://github.com/De-Gregorio/ONDA-programming-language>, 2024. Accessed: 2024-10-03.
- [9] Lov K Grover. A fast quantum mechanical algorithm for database search. In *Proceedings of the twenty-eighth annual ACM symposium on Theory of computing*, pages 212–219, 1996.
- [10] Youngseok Kim, Andrew Eddins, Sajant Anand, Ken Xuan Wei, Ewout van den Berg, Sami Rosenblatt, Hasan Nayfeh, Yantao Wu, Michael Zaletel, Kristan Temme, and Abhinav Kandala. Evidence for the utility of quantum computing before fault tolerance. *Nature*, 618(7965):500–505, Jun 2023.
- [11] F. Orts, G. Ortega, and E. M. Garzón. An optimized quantum circuit for converting from sign-magnitude to two’s complement. *Quantum Information Processing*, 18(11):332, 2019.
- [12] Daniel K. Park, Francesco Petruccione, and June-Koo Kevin Rhee. Circuit-based quantum random access memory for classical data. *Scientific Reports*, 9(1):3949, 2019.
- [13] Junchao Wang and Ken Choi. A carry look-ahead adder designed by reversible logic. In *2014 International SoC Design Conference (ISOCC)*, pages 216–217, 2014.
- [14] Wen-Ling Xu, Tie-Jun Wang, and Chuan Wang. Efficient teleportation for high-dimensional quantum computing. *IEEE Access*, 7:115331–115338, 2019.